## TTK4900 Driver documentation

Generated by Doxygen 1.9.1

1 Class Index	1
1.1 Class List	. 1
2 File Index	3
2.1 File List	. 3
3 Class Documentation	5
3.1 accelerometer_inData Struct Reference	. 5
3.1.1 Detailed Description	. 6
3.1.2 Member Data Documentation	. 6
3.1.2.1 newXAcc	. 6
3.1.2.2 newXRot	. 6
3.1.2.3 newYAcc	. 6
3.1.2.4 newYRot	. 6
3.1.2.5 newZAcc	. 6
3.1.2.6 newZRot	. 7
3.1.2.7 xAcc	. 7
3.1.2.8 xRot	. 7
3.1.2.9 yAcc	. 7
3.1.2.10 yRot	. 7
3.1.2.11 zAcc	. 7
3.1.2.12 zRot	. 8
3.2 can_mailbox Struct Reference	. 8
3.2.1 Detailed Description	. 8
3.2.2 Member Data Documentation	. 8
3.2.2.1 data	. 8
3.2.2.2 msgld	. 8
3.2.2.3 newMsg	. 9
3.3 current_measurement_descriptor Struct Reference	. 9
3.3.1 Detailed Description	
3.3.2 Member Data Documentation	
3.3.2.1 adc	
3.3.2.2 Aipropi	
3.3.2.3 conversionConst	
3.3.2.4 lastMeasurement	
3.3.2.5 lastReading	
3.3.2.6 Nadc	
3.3.2.7 Ripropi	
3.3.2.8 VrefA	
3.4 imu_descriptor Struct Reference	
3.4.1 Detailed Description	
3.4.2 Member Data Documentation	
3.4.2.1 i2cHandle	
· · · · · · · · · · · · · · · · · · ·	

3.4.2.2 readAddr	 . 12
3.4.2.3 writeAddr	 . 12
3.4.2.4 xAccAddr	 . 12
3.4.2.5 xRotAddr	 . 12
3.4.2.6 yAccAddr	 . 13
3.4.2.7 yRotAddr	 . 13
3.4.2.8 zAccAddr	 . 13
3.4.2.9 zRotAddr	 . 13
3.5 joint_controller_descriptor Struct Reference	 . 13
3.5.1 Detailed Description	 . 14
3.5.2 Member Data Documentation	 . 14
3.5.2.1 hasAccelerometer	 . 14
3.5.2.2 intError	 . 15
3.5.2.3 isMoving	 . 15
3.5.2.4 jointName	 . 15
3.5.2.5 Kd	 . 15
3.5.2.6 Kp	 . 15
3.5.2.7 KpTi	 . 15
3.5.2.8 motorNum	 . 16
3.5.2.9 posCurrent	 . 16
3.5.2.10 posError	 . 16
3.5.2.11 posSetpoint	 . 16
3.5.2.12 power	 . 16
3.5.2.13 prevError	 . 16
3.5.2.14 prevPos	 . 17
3.5.2.15 prevPower	 . 17
3.5.2.16 sigmoidIntGain	 . 17
3.6 motor_descriptor Struct Reference	 . 17
3.6.1 Detailed Description	 . 18
3.6.2 Member Data Documentation	 . 18
3.6.2.1 encoderInitCount	 . 18
3.6.2.2 encoderPreviousCount	 . 18
3.6.2.3 encoderTimer	 . 18
3.6.2.4 encoderTotalCount	 . 19
3.6.2.5 encoderTotalInit	 . 19
3.6.2.6 encoderTotalSetpoint	 . 19
3.6.2.7 isMoving	 . 19
3.6.2.8 mostRecentDelta	 . 19
3.6.2.9 motorld	 . 19
3.6.2.10 motorName	 . 20
3.6.2.11 motorPolarity	 . 20
3.6.2.12 motorTimer	 . 20

3.6.2.13 resolution	20
3.6.2.14 torqueConst	20
3.6.2.15 voltageLimit	20
3.6.2.16 voltagePctCap	21
3.7 string_cmd_pair Struct Reference	21
3.7.1 Detailed Description	21
3.7.2 Member Data Documentation	21
3.7.2.1 cmdFuncPointer	21
3.7.2.2 cmdString	21
3.8 string_cmd_processor_args Struct Reference	22
3.8.1 Detailed Description	22
3.8.2 Member Data Documentation	22
3.8.2.1 inputString	22
3.8.2.2 stringLength	22
4 File Documentation	23
4.1 accelerometer_driver.h File Reference	23 23
4.1.1 Detailed Description	24
4.1.2 Function Documentation	24
4.1.2.1 accl_driver_get_x_acc()	24
4.1.2.2 accl_driver_get_x_rot()	25
4.1.2.3 accl_driver_get_y_acc()	25
4.1.2.4 accl_driver_get_y_rot()	25
4.1.2.5 accl_driver_get_z_acc()	26
4.1.2.6 accl_driver_get_z_rot()	26
4.1.2.7 accl_driver_read_byte()	26
4.1.2.8 accl_driver_read_register()	27
4.1.2.9 accl_driver_set_byte()	27
4.1.2.10 accl_interface_get_x_acc()	28
4.1.2.11 accl_interface_get_x_rot()	28
4.1.2.12 accl_interface_get_y_acc()	28
4.1.2.13 accl_interface_get_y_rot()	28
4.1.2.14 accl_interface_get_z_acc()	29
4.1.2.15 accl_interface_get_z_rot()	29
4.1.2.16 accl_interface_read_byte()	29
4.1.2.17 accl_interface_read_register()	29
4.1.2.18 accl_interface_set_byte()	30
4.2 adc_driver.h File Reference	30
4.2.1 Detailed Description	31
4.2.2 Function Documentation	31
4.2.2.1 adc_driver_calculate_current()	31
4.2.2.2 adc_driver_update_measurement()	

4.2.2.3 adc_driver_update_reading()	32
4.2.2.4 adc_interface_get_current()	32
4.2.2.5 adc_interface_update_current()	32
4.3 can_driver.h File Reference	32
4.3.1 Detailed Description	35
4.3.2 Macro Definition Documentation	35
4.3.2.1 CAN_ACC_CMD_OFFSET	35
4.3.2.2 CAN_GBL_CMD_OFFSET	35
4.3.2.3 CAN_MOTOR_CMD_OFFSET	35
4.3.3 Enumeration Type Documentation	35
4.3.3.1 can_message_type	35
4.3.4 Function Documentation	36
4.3.4.1 can_cmd_handle_axisData()	36
4.3.4.2 can_cmd_handle_axisReq()	36
4.3.4.3 can_cmd_handle_dualJointSp()	37
4.3.4.4 can_cmd_handle_inState()	37
4.3.4.5 can_cmd_handle_motorSp()	37
4.3.4.6 can_cmd_handle_pinchTwistSp()	38
4.3.4.7 can_cmd_handle_regReq()	38
4.3.4.8 can_cmd_handle_regVal()	38
4.3.4.9 can_cmd_handle_wristElbowSp()	39
4.3.4.10 can_cmd_handle_yAcc()	39
4.3.4.11 can_driver_cmd_rx0()	39
4.3.4.12 can_driver_cmd_rx1()	39
4.3.4.13 can_driver_cmd_rx2()	40
4.3.4.14 can_driver_cmd_rx3()	40
4.3.4.15 can_driver_cmd_rx4()	40
4.3.4.16 can_driver_cmd_rx5()	41
4.3.4.17 can_driver_cmd_rx6()	41
4.3.4.18 can_driver_cmd_rx7()	41
4.3.4.19 can_driver_cmd_rx8()	41
4.3.4.20 can_driver_cmd_rx9()	42
4.3.4.21 can_driver_cmd_rxA()	42
4.3.4.22 can_driver_cmd_rxB()	42
4.3.4.23 can_driver_cmd_rxC()	43
4.3.4.24 can_driver_cmd_rxD()	43
4.3.4.25 can_driver_cmd_rxE()	43
4.3.4.26 can_driver_queue_tx()	44
4.3.4.27 can_driver_send_msg()	44
4.3.4.28 can_interface_queue_tx()	44
4.3.4.29 can_interface_send_msg()	45
4.3.4.30 can mailbox clear flag()	45

4.3.4.31 can_mailbox_get_data()	45
4.3.4.32 can_mailbox_get_flag()	46
4.3.4.33 can_mailbox_get_id()	46
4.3.4.34 can_mailbox_set_data()	46
4.3.4.35 can_mailbox_set_flag()	47
4.3.4.36 can_mailbox_set_id()	47
4.3.4.37 can_rx_executive()	47
4.3.4.38 can_tx_executive()	47
4.4 gpio_driver.h File Reference	48
4.4.1 Detailed Description	48
4.4.2 Function Documentation	48
4.4.2.1 gpio_end_switch_handler()	48
4.4.2.2 gpio_twist_switch_handler()	48
4.5 joint_controller.h File Reference	49
4.5.1 Detailed Description	52
4.5.2 Function Documentation	52
4.5.2.1 controller_acc_clear_newX()	53
4.5.2.2 controller_acc_clear_newY()	53
4.5.2.3 controller_acc_clear_newZ()	53
4.5.2.4 controller_acc_get_newX()	53
4.5.2.5 controller_acc_get_newY()	53
4.5.2.6 controller_acc_get_newZ()	53
4.5.2.7 controller_acc_getX()	53
4.5.2.8 controller_acc_getY()	54
4.5.2.9 controller_acc_getZ()	54
4.5.2.10 controller_acc_set_newX()	54
4.5.2.11 controller_acc_set_newY()	54
4.5.2.12 controller_acc_set_newZ()	54
4.5.2.13 controller_acc_setX()	54
4.5.2.14 controller_acc_setY()	54
4.5.2.15 controller_acc_setZ()	55
4.5.2.16 controller_interface_acc_clear_newX()	55
4.5.2.17 controller_interface_acc_clear_newY()	55
4.5.2.18 controller_interface_acc_clear_newZ()	55
4.5.2.19 controller_interface_acc_get_newX()	56
4.5.2.20 controller_interface_acc_get_newY()	56
4.5.2.21 controller_interface_acc_get_newZ()	56
4.5.2.22 controller_interface_acc_getX()	57
4.5.2.23 controller_interface_acc_getY()	57
4.5.2.24 controller_interface_acc_getZ()	57
4.5.2.25 controller_interface_acc_set_newX()	58
4.5.2.26 controller_interface_acc_set_newY()	58

4.5.2.27 controller_interface_acc_set_newZ()
4.5.2.28 controller_interface_acc_setX()
4.5.2.29 controller_interface_acc_setY()
4.5.2.30 controller_interface_acc_setZ()
4.5.2.31 controller_interface_clear_acc_poll()
4.5.2.32 controller_interface_clear_moving()
4.5.2.33 controller_interface_clear_mtr_poll()
4.5.2.34 controller_interface_clear_upd_ctrl()
4.5.2.35 controller_interface_clear_upd_telemetry()
4.5.2.36 controller_interface_clicks_to_pos()
4.5.2.37 controller_interface_get_acc_poll()
4.5.2.38 controller_interface_get_error()
4.5.2.39 controller_interface_get_moving()
4.5.2.40 controller_interface_get_mtr_poll()
4.5.2.41 controller_interface_get_position()
4.5.2.42 controller_interface_get_setpoint()
4.5.2.43 controller_interface_get_upd_ctrl()
4.5.2.44 controller_interface_get_upd_telemetry()
4.5.2.45 controller_interface_request_acc_axis()
4.5.2.46 controller_interface_rot_clear_newX()
4.5.2.47 controller_interface_rot_clear_newY()
4.5.2.48 controller_interface_rot_clear_newZ()
4.5.2.49 controller_interface_rot_get_newX()
4.5.2.50 controller_interface_rot_get_newY()
4.5.2.51 controller_interface_rot_get_newZ()
4.5.2.52 controller_interface_rot_getX()
4.5.2.53 controller_interface_rot_getY()
4.5.2.54 controller_interface_rot_getZ()
4.5.2.55 controller_interface_rot_set_newX()
4.5.2.56 controller_interface_rot_set_newY()
4.5.2.57 controller_interface_rot_set_newZ()
4.5.2.58 controller_interface_rot_setX()
4.5.2.59 controller_interface_rot_setY()
4.5.2.60 controller_interface_rot_setZ()
4.5.2.61 controller_interface_set_acc_poll()
4.5.2.62 controller_interface_set_error()
4.5.2.63 controller_interface_set_moving()
4.5.2.64 controller_interface_set_mtr_poll()
4.5.2.65 controller_interface_set_position()
4.5.2.66 controller_interface_set_power()
4.5.2.67 controller_interface_set_setpoint()
4.5.2.68 controller_interface_set_upd_ctrl()

4.5.2.69 controller_interface_set_upd_telemetry()	70
4.5.2.70 controller_interface_update_controller()	70
4.5.2.71 controller_interface_update_error()	70
4.5.2.72 controller_interface_update_position()	70
4.5.2.73 controller_interface_update_power()	71
4.5.2.74 controller_rot_clear_newX()	71
4.5.2.75 controller_rot_clear_newY()	71
4.5.2.76 controller_rot_clear_newZ()	71
4.5.2.77 controller_rot_get_newX()	71
4.5.2.78 controller_rot_get_newY()	72
4.5.2.79 controller_rot_get_newZ()	72
4.5.2.80 controller_rot_getX()	72
4.5.2.81 controller_rot_getY()	72
4.5.2.82 controller_rot_getZ()	72
4.5.2.83 controller_rot_set_newX()	72
4.5.2.84 controller_rot_set_newY()	72
4.5.2.85 controller_rot_set_newZ()	73
4.5.2.86 controller_rot_setX()	73
4.5.2.87 controller_rot_setY()	73
4.5.2.88 controller_rot_setZ()	73
4.5.2.89 joint_controller_acceleration_to_angle()	73
4.5.2.90 joint_controller_adjust_enc_sp()	73
4.5.2.91 joint_controller_clear_moving()	74
4.5.2.92 joint_controller_clicks_to_pos()	74
4.5.2.93 joint_controller_get_error()	74
4.5.2.94 joint_controller_get_moving()	74
4.5.2.95 joint_controller_get_position()	74
4.5.2.96 joint_controller_get_setpoint()	74
4.5.2.97 joint_controller_request_acc_axis()	74
4.5.2.98 joint_controller_set_error()	75
4.5.2.99 joint_controller_set_moving()	75
4.5.2.100 joint_controller_set_position()	75
4.5.2.101 joint_controller_set_power()	75
4.5.2.102 joint_controller_set_setpoint()	75
4.5.2.103 joint_controller_update_error()	75
4.5.2.104 joint_controller_update_position()	76
4.5.2.105 joint_controller_update_power()	76
4.6 motor_driver.h File Reference	76
4.6.1 Detailed Description	78
4.6.2 Function Documentation	78
4.6.2.1 motor_driver_calc_safe_vlt()	78
4.6.2.2 motor_driver_calculate_torqe()	78

4.6.2.3 motor_driver_delta_setpoint()	 . 79
4.6.2.4 motor_driver_get_delta()	 . 79
4.6.2.5 motor_driver_get_encoder_cnt()	 . 79
4.6.2.6 motor_driver_get_id()	 . 80
4.6.2.7 motor_driver_get_moving()	 . 80
4.6.2.8 motor_driver_get_resolution()	 . 80
4.6.2.9 motor_driver_get_setpoint()	 . 81
4.6.2.10 motor_driver_get_total_cnt()	 . 81
4.6.2.11 motor_driver_go_backward()	 . 81
4.6.2.12 motor_driver_go_forward()	 . 82
4.6.2.13 motor_driver_set_power()	 . 82
4.6.2.14 motor_driver_set_pwm_dc()	 . 82
4.6.2.15 motor_driver_set_setpoint()	 . 83
4.6.2.16 motor_driver_set_total_count()	 . 83
4.6.2.17 motor_driver_update_power()	 . 83
4.6.2.18 motor_driver_update_tot_cnt()	 . 84
4.6.2.19 motor_driver_zero()	 . 84
4.6.2.20 motor_interface_calculate_torque()	 . 84
4.6.2.21 motor_interface_delta_setpoint()	 . 85
4.6.2.22 motor_interface_get_delta()	 . 85
4.6.2.23 motor_interface_get_encoder_count()	 . 85
4.6.2.24 motor_interface_get_id()	 . 86
4.6.2.25 motor_interface_get_moving()	 . 86
4.6.2.26 motor_interface_get_resolution()	 . 86
4.6.2.27 motor_interface_get_setpoint()	 . 87
4.6.2.28 motor_interface_get_total_count()	 . 87
4.6.2.29 motor_interface_set_power()	 . 87
4.6.2.30 motor_interface_set_setpoint()	 . 88
4.6.2.31 motor_interface_set_total_count()	 . 88
4.6.2.32 motor_interface_update_power()	 . 88
4.6.2.33 motor_interface_update_tot_cnt()	 . 89
4.6.2.34 motor_interface_zero()	 . 89
4.7 ros_uart_parser.h File Reference	 . 89
4.7.1 Detailed Description	 . 90
4.7.2 Function Documentation	 . 90
4.7.2.1 ros_interface_clear_newMsgFlag()	 . 90
4.7.2.2 ros_interface_clear_rxBuffer()	 . 90
4.7.2.3 ros_interface_get_newMsgFlag()	 . 90
4.7.2.4 ros_interface_get_rxBuffer()	 . 91
4.7.2.5 ros_interface_parse_input()	 . 91
4.7.2.6 ros_interface_set_newMsgFlag()	 . 91
4.7.2.7 ros_interface_set_pinchPos()	 . 91

4.7.2.8 ros_interface_set_rxBuffer()	91
4.8 state_machine.h File Reference	91
4.8.1 Detailed Description	92
4.8.2 Enumeration Type Documentation	92
4.8.2.1 calibration_state	92
4.8.2.2 global_state	93
4.8.3 Function Documentation	93
4.8.3.1 state_calibrate_elbow()	93
4.8.3.2 state_calibrate_pinch()	93
4.8.3.3 state_calibrate_rail()	93
4.8.3.4 state_calibrate_shoulder()	94
4.8.3.5 state_calibrate_twist()	94
4.8.3.6 state_calibrate_wrist()	94
4.8.3.7 state_interface_broadcast_calibration_state()	94
4.8.3.8 state_interface_broadcast_global_state()	94
4.8.3.9 state_interface_clear_es_flag()	94
4.8.3.10 state_interface_clear_tw_flag()	94
4.8.3.11 state_interface_get_calibration_state()	94
4.8.3.12 state_interface_get_es_flag()	95
4.8.3.13 state_interface_get_global_state()	95
4.8.3.14 state_interface_get_tw_flag()	95
4.8.3.15 state_interface_set_calibration_state()	95
4.8.3.16 state_interface_set_es_flag()	95
4.8.3.17 state_interface_set_global_state()	95
4.8.3.18 state_interface_set_tw_flag()	95
4.9 string_cmd_parser.h File Reference	96
4.9.1 Detailed Description	97
4.9.2 Macro Definition Documentation	97
4.9.2.1 NUM_STRING_COMMANDS	97
4.9.2.2 string_cmd_processor	98
4.9.3 Function Documentation	98
4.9.3.1 string_cmd_acc1()	98
4.9.3.2 string_cmd_can()	98
4.9.3.3 string_cmd_category_accelerometer()	98
4.9.3.4 string_cmd_category_adc()	98
4.9.3.5 string_cmd_category_local_motor()	99
4.9.3.6 string_cmd_category_remote_motor()	99
4.9.3.7 string_cmd_elbow()	99
4.9.3.8 string_cmd_home()	99
4.9.3.9 string_cmd_pinch()	100
4.9.3.10 string_cmd_processor_base()	100
4.9.3.11 string_cmd_processor_wrp()	100

4.9.3.12 string_cmd_rail()	. 101
4.9.3.13 string_cmd_rly()	. 101
4.9.3.14 string_cmd_shoulder()	. 101
4.9.3.15 string_cmd_state()	. 101
4.9.3.16 string_cmd_stop()	. 102
4.9.3.17 string_cmd_twist()	. 102
4.9.3.18 string_cmd_wrist()	. 102
4.9.4 Variable Documentation	. 103
4.9.4.1 stringCmdList	. 103
4.10 uart_driver.h File Reference	. 103
4.10.1 Detailed Description	. 104
4.10.2 Function Documentation	. 104
4.10.2.1 uart_hmi_init()	. 104
4.10.2.2 uart_hmi_rx_handler()	. 104
4.10.2.3 uart_parse_hmi_input()	. 104
4.10.2.4 uart_parse_ros_input()	. 105
4.10.2.5 uart_ros_init()	. 105
4.10.2.6 uart_ros_rx_handler()	. 105
4.10.2.7 uart_send_string()	. 105
4.11 unit_config.h File Reference	. 105
4.11.1 Detailed Description	. 106
4.11.2 Macro Definition Documentation	. 106
4.11.2.1 ACTIVE_UNIT	. 107
4.11.2.2 CAN_FILTER_A	. 107
4.11.2.3 CAN_FILTER_G	. 107
4.11.2.4 CAN_FILTER_M	. 107
4.11.2.5 CAN_FILTERMASK_A	. 107
4.11.2.6 CAN_FILTERMASK_G	. 107
4.11.2.7 CAN_FILTERMASK_M	. 107
4.11.2.8 CMD_MODE_ROS	. 107
4.11.2.9 CMD_MODE_TERMINAL	. 108
4.11.2.10 ENC1	. 108
4.11.2.11 ENC2	. 108
4.11.2.12 GLOBAL_DEBUG	. 108
4.11.2.13 HAND	. 108
4.11.2.14 HW_INTERFACE	. 108
4.11.2.15 MTR1	. 108
4.11.2.16 MTR2	. 108
4.11.2.17 PWM_CTR_PRD	. 109
4.11.2.18 SHOULDER	. 109
4.11.2.19 SW_INTERFACE	. 109
4.11.2.20 TORSO	. 109

Index		111
	4.11.3.1 activate_peripherals()	109
	4.11.3 Function Documentation	109
	4.11.2.24 VOLTAGE_IN	109
	4.11.2.23 USB_INTERFACE	109
	4.11.2.22 UART_INTERFACE	109
	4.11.2.21 UART_INPUT	109

# **Chapter 1**

# **Class Index**

## 1.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

accelerometer_inData	
Holds INCOMING accelerometer data, NOT part of the accelerometer driver	5
can_mailbox	
A virtual CAN mailbox for outgoing and incoming messages	8
current_measurement_descriptor	
Database with key information for the motor current sensing ADCs	9
imu_descriptor	
Key information about the IMUs	11
joint_controller_descriptor	
Joint controller information database	13
motor_descriptor	
Contains static and state information relevant to the operation of a motor driver	17
string_cmd_pair	
Pairs a command string token with a function pointer	21
string_cmd_processor_args	
Wrapper struct to enable a variable number of arguments to the string processor	22

2 Class Index

# Chapter 2

# File Index

## 2.1 File List

Here is a list of all files with brief descriptions:

accelerometer_driver.h	
This file contains all the function prototypes and struct definitions for the accelerometer_driver.c	
file	23
adc_driver.h	
This file contains all the function prototypes and struct definitions for the adc_driver.c file	30
can_driver.h	
This file contains all the function prototypes and struct definitions for the can_driver.c file	32
gpio_driver.h	
This file contains all the function prototypes for the gpio_driver.c file	48
joint_controller.h	
This file contains all the function prototypes and struct definitions for the joint_controller.c file .	49
motor_driver.h	
This file contains all the function prototypes and struct definitions for the motor_driver.c file	76
ros_uart_parser.h	
This file contains all the function prototypes for the ros_uart_parser.c file	89
state_machine.h	
This file contains all the function prototypes and struct definitions for the state_machine.c file .	91
string_cmd_parser.h	
This file contains all the function prototypes and struct definitions for the string_cmd_parser.c file	96
uart_driver.h	
This file contains all the function prototypes for the string_cmd_parser.c file	103
unit_config.h	
This file contains global information relevant to building the project for a specific STM32 in the	
robotic arm	105

File Index

## **Chapter 3**

## **Class Documentation**

## 3.1 accelerometer\_inData Struct Reference

Holds INCOMING accelerometer data, NOT part of the accelerometer driver.

```
#include <joint_controller.h>
```

## **Public Attributes**

• int16\_t xAcc

X axis acceleration.

int16\_t xRot

X axis rotation.

int16\_t yAcc

Y axis acceleration.

int16\_t yRot

Y axis rotation.

• int16\_t zAcc

Z axis acceleration.

• int16\_t zRot

Z axis rotation.

uint8\_t newXAcc

Flags new X acceleration data on arrival.

uint8\_t newYAcc

Flags new Y acceleration data on arrival.

uint8\_t newZAcc

Flags new Z acceleration data on arrival.

uint8\_t newXRot

Flags new X rotation data on arrival.

• uint8\_t newYRot

Flags new Y rotation data on arrival.

uint8\_t newZRot

Flags new Z rotation data on arrival.

## 3.1.1 Detailed Description

Holds INCOMING accelerometer data, NOT part of the accelerometer driver.

## 3.1.2 Member Data Documentation

#### 3.1.2.1 newXAcc

uint8\_t accelerometer\_inData::newXAcc

Flags new X acceleration data on arrival.

#### 3.1.2.2 newXRot

uint8\_t accelerometer\_inData::newXRot

Flags new X rotation data on arrival.

## 3.1.2.3 newYAcc

uint8\_t accelerometer\_inData::newYAcc

Flags new Y acceleration data on arrival.

## 3.1.2.4 newYRot

uint8\_t accelerometer\_inData::newYRot

Flags new Y rotation data on arrival.

## 3.1.2.5 newZAcc

uint8\_t accelerometer\_inData::newZAcc

Flags new Z acceleration data on arrival.

## 3.1.2.6 newZRot

uint8\_t accelerometer\_inData::newZRot

Flags new Z rotation data on arrival.

#### 3.1.2.7 xAcc

int16\_t accelerometer\_inData::xAcc

X axis acceleration.

## 3.1.2.8 xRot

int16\_t accelerometer\_inData::xRot

X axis rotation.

## 3.1.2.9 yAcc

int16\_t accelerometer\_inData::yAcc

Y axis acceleration.

## 3.1.2.10 yRot

int16\_t accelerometer\_inData::yRot

Y axis rotation.

## 3.1.2.11 zAcc

int16\_t accelerometer\_inData::zAcc

Z axis acceleration.

## 3.1.2.12 zRot

```
int16_t accelerometer_inData::zRot
```

Z axis rotation.

The documentation for this struct was generated from the following file:

• joint\_controller.h

## 3.2 can\_mailbox Struct Reference

A virtual CAN mailbox for outgoing and incoming messages.

```
#include <can_driver.h>
```

#### **Public Attributes**

uint8\_t newMsg

Flag signifying that the mailbox contains an unhandled message.

• uint32\_t msgld

CAN message ID, 11 bits (standard ID)

uint8\_t data [8]

CAN message data.

## 3.2.1 Detailed Description

A virtual CAN mailbox for outgoing and incoming messages.

## 3.2.2 Member Data Documentation

#### 3.2.2.1 data

```
uint8_t can_mailbox::data[8]
```

CAN message data.

## 3.2.2.2 msgld

```
uint32_t can_mailbox::msgId
```

CAN message ID, 11 bits (standard ID)

#### 3.2.2.3 newMsg

```
uint8_t can_mailbox::newMsg
```

Flag signifying that the mailbox contains an unhandled message.

The documentation for this struct was generated from the following file:

· can\_driver.h

## 3.3 current\_measurement\_descriptor Struct Reference

Database with key information for the motor current sensing ADCs.

```
#include <adc_driver.h>
```

## **Public Attributes**

· double VrefA

Analog reference voltage, V.

• double Ripropi

Current sense resistor, Ohm.

• double Aipropi

Current sense proportional current, uA/A.

• uint32\_t Nadc

ADC saturation point.

• ADC\_HandleTypeDef \* adc

ADC for current measurement.

double conversionConst

Constant number for conversion of ADC value to Ampere.

uint32\_t lastReading

Latest ADC raw value.

• double lastMeasurement

Latest calculated current.

## 3.3.1 Detailed Description

Database with key information for the motor current sensing ADCs.

## 3.3.2 Member Data Documentation

## 3.3.2.1 adc

ADC\_HandleTypeDef\* current\_measurement\_descriptor::adc

ADC for current measurement.

## 3.3.2.2 Aipropi

double current\_measurement\_descriptor::Aipropi

Current sense proportional current, uA/A.

#### 3.3.2.3 conversionConst

double current\_measurement\_descriptor::conversionConst

Constant number for conversion of ADC value to Ampere.

## 3.3.2.4 lastMeasurement

double current\_measurement\_descriptor::lastMeasurement

Latest calculated current.

## 3.3.2.5 lastReading

uint32\_t current\_measurement\_descriptor::lastReading

Latest ADC raw value.

#### 3.3.2.6 Nadc

uint32\_t current\_measurement\_descriptor::Nadc

ADC saturation point.

#### 3.3.2.7 Ripropi

double current\_measurement\_descriptor::Ripropi

Current sense resistor, Ohm.

## 3.3.2.8 VrefA

double current\_measurement\_descriptor::VrefA

Analog reference voltage, V.

The documentation for this struct was generated from the following file:

• adc\_driver.h

## 3.4 imu\_descriptor Struct Reference

Key information about the IMUs.

#include <accelerometer\_driver.h>

## **Public Attributes**

• I2C\_HandleTypeDef \* i2cHandle

Pointer to the I2C bus peripheral.

· uint16 t readAddr

Read address of the IMU on the I2C bus.

uint16\_t writeAddr

Write address of the IMU on the I2C bus.

uint8\_t xAccAddr

Start address of the IMU's X axis accelerometer register.

uint8\_t yAccAddr

Start address of the IMU's Y axis accelerometer register.

uint8\_t zAccAddr

Start address of the IMU's Z axis accelerometer register.

uint8\_t xRotAddr

Start address of the IMU's X axis rotation rate register.

uint8\_t yRotAddr

Start address of the IMU's Y axis rotation rate register.

uint8\_t zRotAddr

Start address of the IMU's Z axis rotation rate register.

## 3.4.1 Detailed Description

Key information about the IMUs.

## 3.4.2 Member Data Documentation

#### 3.4.2.1 i2cHandle

I2C\_HandleTypeDef\* imu\_descriptor::i2cHandle

Pointer to the I2C bus peripheral.

## 3.4.2.2 readAddr

uint16\_t imu\_descriptor::readAddr

Read address of the IMU on the I2C bus.

## 3.4.2.3 writeAddr

uint16\_t imu\_descriptor::writeAddr

Write address of the IMU on the I2C bus.

#### 3.4.2.4 xAccAddr

uint8\_t imu\_descriptor::xAccAddr

Start address of the IMU's X axis accelerometer register.

## 3.4.2.5 xRotAddr

uint8\_t imu\_descriptor::xRotAddr

Start address of the IMU's X axis rotation rate register.

## 3.4.2.6 yAccAddr

```
uint8_t imu_descriptor::yAccAddr
```

Start address of the IMU's Y axis accelerometer register.

#### 3.4.2.7 yRotAddr

```
uint8_t imu_descriptor::yRotAddr
```

Start address of the IMU's Y axis rotation rate register.

#### 3.4.2.8 zAccAddr

```
uint8_t imu_descriptor::zAccAddr
```

Start address of the IMU's Z axis accelerometer register.

## 3.4.2.9 zRotAddr

```
uint8_t imu_descriptor::zRotAddr
```

Start address of the IMU's Z axis rotation rate register.

The documentation for this struct was generated from the following file:

• accelerometer\_driver.h

## 3.5 joint\_controller\_descriptor Struct Reference

Joint controller information database.

```
#include <joint_controller.h>
```

## **Public Attributes**

• uint8\_t hasAccelerometer

Whether the joint has an accelerometer for position control.

float posSetpoint

The joint's setpoint in radians/mm relative to its zero position.

float posCurrent

The joint's current position in radians/mm relative to its zero position.

float prevPos

The joint's position in the previous timestep.

· float posError

The joint's position error in radians/mm, relative to its setpoint.

float prevError

The joint's positional error in the previous timestep.

· float power

Current power setting of the joint.

float prevPower

The joint's power setting in the previous timestep.

uint8 t isMoving

Whether the joint is in a "moving" state.

uint8\_t motorNum

Link to the corresponding motor\_descriptor.

• uint8\_t sigmoidIntGain

Whether or not the joint should use sigmoid integral gain.

float Kp

PID controller Kp.

float KpTi

PID controller Kp/Ti.

float Kd

PID controller Kd.

float intError

Positional integral error.

• uint8\_t \* jointName

The joint's human readable name. This field must be last.

## 3.5.1 Detailed Description

Joint controller information database.

## 3.5.2 Member Data Documentation

#### 3.5.2.1 hasAccelerometer

uint8\_t joint\_controller\_descriptor::hasAccelerometer

Whether the joint has an accelerometer for position control.

## 3.5.2.2 intError

float joint\_controller\_descriptor::intError

Positional integral error.

#### 3.5.2.3 isMoving

uint8\_t joint\_controller\_descriptor::isMoving

Whether the joint is in a "moving" state.

## 3.5.2.4 jointName

uint8\_t\* joint\_controller\_descriptor::jointName

The joint's human readable name. This field must be last.

## 3.5.2.5 Kd

float joint\_controller\_descriptor::Kd

PID controller Kd.

## 3.5.2.6 Kp

float joint\_controller\_descriptor::Kp

PID controller Kp.

## 3.5.2.7 KpTi

float joint\_controller\_descriptor::KpTi

PID controller Kp/Ti.

## 3.5.2.8 motorNum

```
uint8_t joint_controller_descriptor::motorNum
```

Link to the corresponding motor\_descriptor.

## 3.5.2.9 posCurrent

```
\verb|float joint_controller_descriptor::posCurrent|\\
```

The joint's current position in radians/mm relative to its zero position.

## 3.5.2.10 posError

```
float joint_controller_descriptor::posError
```

The joint's position error in radians/mm, relative to its setpoint.

## 3.5.2.11 posSetpoint

```
float joint_controller_descriptor::posSetpoint
```

The joint's setpoint in radians/mm relative to its zero position.

## 3.5.2.12 power

```
float joint_controller_descriptor::power
```

Current power setting of the joint.

## 3.5.2.13 prevError

```
float joint_controller_descriptor::prevError
```

The joint's positional error in the previous timestep.

#### 3.5.2.14 prevPos

```
float joint_controller_descriptor::prevPos
```

The joint's position in the previous timestep.

#### 3.5.2.15 prevPower

```
float joint_controller_descriptor::prevPower
```

The joint's power setting in the previous timestep.

## 3.5.2.16 sigmoidIntGain

```
uint8_t joint_controller_descriptor::sigmoidIntGain
```

Whether or not the joint should use sigmoid integral gain.

The documentation for this struct was generated from the following file:

• joint\_controller.h

## 3.6 motor\_descriptor Struct Reference

Contains static and state information relevant to the operation of a motor driver.

```
#include <motor driver.h>
```

## **Public Attributes**

· uint8 t motorld

The motor's unique ID, essential for CAN messaging.

uint8\_t voltageLimit

Safe voltage limit, as stated in the motor's datasheet.

uint8\_t voltagePctCap

Safe voltage percentage cap, given by input voltage and safe limit.

int8\_t motorPolarity

The motor's polarity, which pole is connected to +/- on the driver.

• TIM\_TypeDef \* motorTimer

The MCU timer peripheral which drives the motor.

TIM\_TypeDef \* encoderTimer

The MCU timer peripheral which registers the motor's encoder.

int32\_t resolution

Relation between number of encoder clicks per mm or rad of movement.

float torqueConst

Motor's torque constant in Nm/A, from datasheet.

• uint16\_t encoderInitCount

Number of encoder clicks counted on startup (nominally 0)

• int32 t encoderTotalInit

Number of total encoder clicks counted on startup (nominally 0)

• int32 t encoderTotalSetpoint

Setpoint for motor encoder count, relevant if circumventing joint controller.

• int32 t encoderTotalCount

Total number of encoder clicks registered since startup.

• int32\_t encoderPreviousCount

The previous total encoder count, used for updating total.

int32\_t mostRecentDelta

The most recently registered increment/decrement in encoder count, essentially movement rate.

uint8\_t isMoving

Whether the motor is moving, assumed true if mostRecentDelta>50.

• char \* motorName

Human readable name of the motor.

## 3.6.1 Detailed Description

Contains static and state information relevant to the operation of a motor driver.

## 3.6.2 Member Data Documentation

#### 3.6.2.1 encoderInitCount

uint16\_t motor\_descriptor::encoderInitCount

Number of encoder clicks counted on startup (nominally 0)

## 3.6.2.2 encoderPreviousCount

 $\verb|int32_t motor_descriptor:: encoder Previous Count|\\$ 

The previous total encoder count, used for updating total.

#### 3.6.2.3 encoderTimer

TIM\_TypeDef\* motor\_descriptor::encoderTimer

The MCU timer peripheral which registers the motor's encoder.

## 3.6.2.4 encoderTotalCount

 $\verb|int32_t motor_descriptor::encoderTotalCount|\\$ 

Total number of encoder clicks registered since startup.

#### 3.6.2.5 encoderTotalInit

int32\_t motor\_descriptor::encoderTotalInit

Number of total encoder clicks counted on startup (nominally 0)

## 3.6.2.6 encoderTotalSetpoint

int32\_t motor\_descriptor::encoderTotalSetpoint

Setpoint for motor encoder count, relevant if circumventing joint controller.

## 3.6.2.7 isMoving

uint8\_t motor\_descriptor::isMoving

Whether the motor is moving, assumed true if mostRecentDelta>50.

## 3.6.2.8 mostRecentDelta

int32\_t motor\_descriptor::mostRecentDelta

The most recently registered increment/decrement in encoder count, essentially movement rate.

#### 3.6.2.9 motorld

uint8\_t motor\_descriptor::motorId

The motor's unique ID, essential for CAN messaging.

## 3.6.2.10 motorName

```
char* motor_descriptor::motorName
```

Human readable name of the motor.

#### 3.6.2.11 motorPolarity

```
int8_t motor_descriptor::motorPolarity
```

The motor's polarity, which pole is connected to +/- on the driver.

#### 3.6.2.12 motorTimer

```
TIM_TypeDef* motor_descriptor::motorTimer
```

The MCU timer peripheral which drives the motor.

## 3.6.2.13 resolution

```
int32_t motor_descriptor::resolution
```

Relation between number of encoder clicks per mm or rad of movement.

## 3.6.2.14 torqueConst

```
float motor_descriptor::torqueConst
```

Motor's torque constant in Nm/A, from datasheet.

## 3.6.2.15 voltageLimit

```
uint8_t motor_descriptor::voltageLimit
```

Safe voltage limit, as stated in the motor's datasheet.

#### 3.6.2.16 voltagePctCap

```
uint8_t motor_descriptor::voltagePctCap
```

Safe voltage percentage cap, given by input voltage and safe limit.

The documentation for this struct was generated from the following file:

· motor\_driver.h

## 3.7 string\_cmd\_pair Struct Reference

Pairs a command string token with a function pointer.

```
#include <string_cmd_parser.h>
```

#### **Public Attributes**

```
\bullet \ \ char * cmdString
```

String token.

void(\* cmdFuncPointer )()

Corresponding handler function.

## 3.7.1 Detailed Description

Pairs a command string token with a function pointer.

#### 3.7.2 Member Data Documentation

## 3.7.2.1 cmdFuncPointer

```
void(* string_cmd_pair::cmdFuncPointer) ()
```

Corresponding handler function.

## 3.7.2.2 cmdString

```
\verb|char*| string_cmd_pair::cmdString|
```

String token.

The documentation for this struct was generated from the following file:

string\_cmd\_parser.h

## 3.8 string\_cmd\_processor\_args Struct Reference

Wrapper struct to enable a variable number of arguments to the string processor.

```
#include <string_cmd_parser.h>
```

#### **Public Attributes**

• char \* inputString [64]

String to be processed.

uint8\_t stringLength

Length of the string to be processed.

## 3.8.1 Detailed Description

Wrapper struct to enable a variable number of arguments to the string processor.

## 3.8.2 Member Data Documentation

## 3.8.2.1 inputString

```
char* string_cmd_processor_args::inputString[64]
```

String to be processed.

## 3.8.2.2 stringLength

```
uint8_t string_cmd_processor_args::stringLength
```

Length of the string to be processed.

The documentation for this struct was generated from the following file:

• string\_cmd\_parser.h

# **Chapter 4**

# **File Documentation**

# 4.1 accelerometer\_driver.h File Reference

This file contains all the function prototypes and struct definitions for the accelerometer\_driver.c file.

```
#include "uart_driver.h"
#include "unit_config.h"
#include "i2c.h"
#include "stdint.h"
#include "string.h"
```

#### **Classes**

· struct imu\_descriptor

Key information about the IMUs.

## **Functions**

```
• uint8_t accl_interface_read_byte (uint8_t regAddr)
```

Module external interface function to read a byte register.

```
• uint16_t accl_interface_read_register (uint8_t regAddr)
```

Module external interface function to read a two-byte register.

int16\_t accl\_interface\_get\_x\_acc ()

Module external interface function to read the IMU's X axis acceleration.

int16\_t accl\_interface\_get\_y\_acc ()

Module external interface function to read the IMU's Y axis acceleration.

int16\_t accl\_interface\_get\_z\_acc ()

Module external interface function to read the IMU's Z axis acceleration.

int16\_t accl\_interface\_get\_x\_rot ()

Module external interface function to read the IMU's X axis rotation.

• int16\_t accl\_interface\_get\_y\_rot ()

Module external interface function to read the IMU's Y axis rotation.

int16\_t accl\_interface\_get\_z\_rot ()

Module external interface function to read the IMU's Z axis rotation.

• void accl\_interface\_set\_byte (uint8\_t regAddr, uint8\_t data)

Module external interface function to write a byte to an IMU register.

uint8\_t accl\_driver\_read\_byte (imu\_descriptor \*imu, uint8\_t regAddr)

Read a single byte register from the IMU.

uint16\_t accl\_driver\_read\_register (imu\_descriptor \*imu, uint8\_t regAddr)

Read a two byte register from the IMU.

• void accl\_driver\_set\_byte (imu\_descriptor \*imu, uint8\_t regAddr, uint8\_t data)

Write single byte register of the IMU.

int16\_t accl\_driver\_get\_x\_acc (imu\_descriptor \*imu)

Read X axis acceleration register.

int16\_t accl\_driver\_get\_y\_acc (imu\_descriptor \*imu)

Read Y axis acceleration register.

• int16\_t accl\_driver\_get\_z\_acc (imu\_descriptor \*imu)

Read X axis acceleration register.

int16\_t accl\_driver\_get\_x\_rot (imu\_descriptor \*imu)

Read X axis rotation register.

• int16\_t accl\_driver\_get\_y\_rot (imu\_descriptor \*imu)

Read Y axis rotation register.

• int16\_t accl\_driver\_get\_z\_rot (imu\_descriptor \*imu)

Read Z axis rotation register.

# 4.1.1 Detailed Description

This file contains all the function prototypes and struct definitions for the accelerometer\_driver.c file.

Attention

IMU driver for the TTK4900 Master project of Kristian Blom, spring semester of 2024. The driver specifies a struct of relevant register addresses from the LSM6DSM IMU as well as functions using the I2C peripheral to read these addresses.

#### 4.1.2 Function Documentation

## 4.1.2.1 accl\_driver\_get\_x\_acc()

Read X axis acceleration register.

**Parameters** 

*imu* Pointer to the relevant IMU struct

Returns

Acceleration raw value

## 4.1.2.2 accl\_driver\_get\_x\_rot()

Read X axis rotation register.

#### **Parameters**

imu Pointer to the relevant IMU struct

Returns

Rotation raw value

# 4.1.2.3 accl\_driver\_get\_y\_acc()

Read Y axis acceleration register.

#### **Parameters**

imu Pointer to the relevant IMU struct

Returns

Acceleration raw value

# 4.1.2.4 accl\_driver\_get\_y\_rot()

Read Y axis rotation register.

#### **Parameters**

imu Pointer to the relevant IMU struct

Returns

Rotation raw value

# 4.1.2.5 accl\_driver\_get\_z\_acc()

Read X axis acceleration register.

#### **Parameters**

imu Pointer to the relevant IMU struct

#### Returns

Acceleration raw value

# 4.1.2.6 accl\_driver\_get\_z\_rot()

Read Z axis rotation register.

## **Parameters**

imu Pointer to the relevant IMU struct

Returns

Rotation raw value

# 4.1.2.7 accl\_driver\_read\_byte()

Read a single byte register from the IMU.

#### **Parameters**

imu	Pointer to the relevant IMU struct
regAddr	Address to read

#### Returns

Value of the register

# 4.1.2.8 accl\_driver\_read\_register()

Read a two byte register from the IMU.

#### **Parameters**

imu	Pointer to the relevant IMU struct
regAddr	Address to start read

## Returns

Concatenated values of the two registers (left shift + bitwOR)

# 4.1.2.9 accl\_driver\_set\_byte()

Write single byte register of the IMU.

## **Parameters**

imu	Pointer to the relevant IMU struct
regAddr	Address to write
data	Data to write

#### 4.1.2.10 accl\_interface\_get\_x\_acc()

```
int16_t accl_interface_get_x_acc ( )
```

Module external interface function to read the IMU's X axis acceleration.

#### Returns

Raw acceleration value as determined by the IMU's configured acceleration resolution

## 4.1.2.11 accl\_interface\_get\_x\_rot()

```
int16_t accl_interface_get_x_rot ( )
```

Module external interface function to read the IMU's X axis rotation.

## Returns

Raw rotation value as determined by the IMU's configured rotation resolution

#### 4.1.2.12 accl\_interface\_get\_y\_acc()

```
int16_t accl_interface_get_y_acc ( )
```

Module external interface function to read the IMU's Y axis acceleration.

#### Returns

Raw acceleration value as determined by the IMU's configured acceleration resolution

# 4.1.2.13 accl\_interface\_get\_y\_rot()

```
int16_t accl_interface_get_y_rot ( )
```

Module external interface function to read the IMU's Y axis rotation.

#### Returns

Raw rotation value as determined by the IMU's configured rotation resolution

## 4.1.2.14 accl\_interface\_get\_z\_acc()

```
int16\_t accl_interface_get_z_acc ( )
```

Module external interface function to read the IMU's Z axis acceleration.

#### Returns

Raw acceleration value as determined by the IMU's configured acceleration resolution

#### 4.1.2.15 accl\_interface\_get\_z\_rot()

```
int16_t accl_interface_get_z_rot ( )
```

Module external interface function to read the IMU's Z axis rotation.

## Returns

Raw rotation value as determined by the IMU's configured rotation resolution

#### 4.1.2.16 accl\_interface\_read\_byte()

Module external interface function to read a byte register.

#### **Parameters**

```
regAddr Address to read
```

## Returns

Value of the register

# 4.1.2.17 accl\_interface\_read\_register()

```
\begin{tabular}{ll} uint16\_t & accl_interface\_read\_register ( \\ & uint8\_t & regAddr ) \end{tabular}
```

Module external interface function to read a two-byte register.

#### **Parameters**

regAddr Start address of	the read
--------------------------	----------

#### Returns

Value of the register

#### 4.1.2.18 accl\_interface\_set\_byte()

Module external interface function to write a byte to an IMU register.

#### **Parameters**

regAddr	Address to write
data	Data to write

# 4.2 adc\_driver.h File Reference

This file contains all the function prototypes and struct definitions for the adc\_driver.c file.

```
#include "stdint.h"
#include "math.h"
#include "adc.h"
#include "unit_config.h"
#include "uart_driver.h"
```

#### **Classes**

• struct current\_measurement\_descriptor

Database with key information for the motor current sensing ADCs.

## **Functions**

• double adc\_interface\_get\_current (uint8\_t sensorSelect)

Module external interface function to read the most recently calculated current.

void adc\_interface\_update\_current (uint8\_t sensorSelect)

Module external interface function to trigger a current calculation.

• double adc\_driver\_calculate\_current (current\_measurement\_descriptor \*sensor)

Calculates current in Ampere based on an ADC raw value.

void adc\_driver\_update\_reading (current\_measurement\_descriptor \*sensor)

Trigger a reading of the relevant ADC, insert into sensor struct.

void adc\_driver\_update\_measurement (current\_measurement\_descriptor \*sensor)

Calculate lastest current measurement, insert into struct.

# 4.2.1 Detailed Description

This file contains all the function prototypes and struct definitions for the adc\_driver.c file.

Attention

ADC driver for the TTK4900 Master project of Kristian Blom, spring semester of 2024. This driver is tailored for use with the current sense pin of the DRV8251A motor driver

## 4.2.2 Function Documentation

# 4.2.2.1 adc\_driver\_calculate\_current()

Calculates current in Ampere based on an ADC raw value.

#### **Parameters**

sensor Pointer to the relevant sensor struct	t
--	---

Returns

Ampere

#### 4.2.2.2 adc\_driver\_update\_measurement()

Calculate lastest current measurement, insert into struct.

# **Parameters**

sensor	Pointer to the relevant sensor struct

#### 4.2.2.3 adc\_driver\_update\_reading()

Trigger a reading of the relevant ADC, insert into sensor struct.

**Parameters** 

sensor Pointer to the relevant sensor struct

## 4.2.2.4 adc\_interface\_get\_current()

Module external interface function to read the most recently calculated current.

#### **Parameters**

sensorSelect	Select from one of two motor current sensor ADCs
--------------	--

# Returns

Latest calculated current measurement

## 4.2.2.5 adc\_interface\_update\_current()

Module external interface function to trigger a current calculation.

# **Parameters**

sensorSelect | Select from of two motor current sensor ADCs

# 4.3 can\_driver.h File Reference

This file contains all the function prototypes and struct definitions for the can\_driver.c file.

```
#include "stdint.h"
#include "can.h"
```

```
#include "unit_config.h"
#include "motor_driver.h"
#include "accelerometer_driver.h"
#include "joint_controller.h"
#include "state_machine.h"
```

#### **Classes**

struct can\_mailbox

A virtual CAN mailbox for outgoing and incoming messages.

#### **Macros**

- #define CAN MOTOR CMD OFFSET 5
- #define CAN ACC CMD OFFSET 8
- #define CAN\_GBL\_CMD\_OFFSET 10

#### **Enumerations**

```
    enum can_message_type {
        ACC_X_TX, ACC_Y_TX, ACC_Z_TX, ACC_REG_RX,
        ACC_REG_REQ, JOINT_POS_SP, MOTOR_VLT_SP, JOINT_POS_REQ,
        JOINT_POS_TX, ACC_X_REQ, ACC_Y_REQ, ACC_Z_REQ,
        GBL_ST_SET, WRIST_ELBOW_SP, PINCH_TWIST_SP, num_types }
        CAN message types.
```

## **Functions**

- void can\_interface\_queue\_tx (uint8\_t mailbox, uint8\_t \*outData, uint32\_t id)
  - Module external function for queueing a CAN message for transmit.
- void can\_interface\_send\_msg (uint8\_t \*data, uint32\_t id, int dlc, uint8\_t hwMailbox)

Public function to send CAN message immediately.

• void can rx executive ()

Looks for new incoming CAN messages and handles them. MAIN LOOP ONLY.

void can\_tx\_executive ()

Looks for new CAN messages to send, sends. MAIN LOOP ONLY.

• void can\_mailbox\_set\_data (can\_mailbox \*mailbox, uint8\_t \*inData)

Sets the data field of the given mailbox.

void can mailbox get data (can mailbox \*mailbox, uint8 t \*target)

Inserts the data field of the given mailbox to target. CAUTION: memcpy 8 bytes.

void can\_mailbox\_set\_flag (can\_mailbox \*mailbox)

Sets the newmsg flag of the given mailbox.

uint8\_t can\_mailbox\_get\_flag (can\_mailbox \*mailbox)

Gets the newmsg flag of the given mailbox.

void can mailbox clear flag (can mailbox \*mailbox)

Clears the newmsg flag of the given mailbox.

void can\_mailbox\_set\_id (can\_mailbox \*mailbox, uint32\_t id)

Sets the CAN message ID field of the given mailbox.

 uint32\_t can\_mailbox\_get\_id (can\_mailbox \*mailbox) Gets the CAN message ID of the given mailbox. • void can driver queue tx (can mailbox \*mailbox, uint8 t \*outData, uint32 t id) Queues a can message for transmit, driver internal. void can\_driver\_send\_msg (uint8\_t \*data, uint32\_t stdld, int dlc, uint8\_t hwMailbox) Sends a CAN message. void can cmd handle vAcc (uint32 t id, uint8 t \*inData) void can cmd handle regVal (uint32 t id, uint8 t \*inData) Handles an incoming accelerometer register message. void can\_cmd\_handle\_regReq (uint32\_t id, uint8\_t \*inData) Handles an incoming accelerometer read request. void can\_cmd\_handle\_motorSp (uint32\_t id, uint8\_t \*inData) Handles an incoming motor setpoint. void can\_cmd\_handle\_axisReq (uint32\_t id, uint8\_t \*inData) Handles an incoming request for accelerometer axis data. void can cmd handle axisData (uint32 t id, uint8 t \*inData) Handles incoming accelerometer axis data. • void can cmd handle inState (uint32 t id, uint8 t \*inData) Handles incoming state information. void can cmd handle dualJointSp (uint32 t id, uint8 t \*inData) Handles incoming setpoints for both joints. void can\_cmd\_handle\_wristElbowSp (uint32\_t id, uint8\_t \*inData) Handles incoming setpoints for elbow and wrist joints. void can\_cmd\_handle\_pinchTwistSp (uint32\_t id, uint8\_t \*inData) Handles incoming setpoints for twist and pinch joints. void can driver cmd rx0 (uint32 t id, uint8 t \*inData) "Generic" function to handle CAN message type ACC\_X\_TX void can driver cmd rx1 (uint32 t id, uint8 t \*inData) "Generic" function to handle CAN message type ACC\_Y\_TX • void can\_driver\_cmd\_rx2 (uint32\_t id, uint8\_t \*inData) "Generic" function to handle CAN message type ACC Z TX void can driver cmd rx3 (uint32 t id, uint8 t \*inData) "Generic" function to handle CAN message type ACC REG RX void can driver cmd rx4 (uint32 t id, uint8 t \*inData) "Generic" function to handle CAN message type ACC REG REQ void can\_driver\_cmd\_rx5 (uint32\_t id, uint8\_t \*inData) "Generic" function to handle CAN message type JOINT\_POS\_SP void can\_driver\_cmd\_rx6 (uint32\_t id, uint8\_t \*inData) "Generic" function to handle CAN message type MOTOR\_VLT\_SP void can\_driver\_cmd\_rx7 (uint32\_t id, uint8\_t \*inData) "Generic" function to handle CAN message type ACC\_X\_TX void can driver cmd rx8 (uint32 t id, uint8 t \*inData) "Generic" function to handle CAN message type JOINT POS TX void can driver cmd rx9 (uint32 t id, uint8 t \*inData) "Generic" function to handle CAN message type ACC X REQ void can\_driver\_cmd\_rxA (uint32\_t id, uint8\_t \*inData) "Generic" function to handle CAN message type ACC Y REQ void can\_driver\_cmd\_rxB (uint32\_t id, uint8\_t \*inData) "Generic" function to handle CAN message type ACC Z REQ

void can\_driver\_cmd\_rxC (uint32\_t id, uint8\_t \*inData)

"Generic" function to handle CAN message type GBL\_ST\_SET

- void can\_driver\_cmd\_rxD (uint32\_t id, uint8\_t \*inData)
  - "Generic" function to handle CAN message type WRIST\_ELBOW\_SP
- void can\_driver\_cmd\_rxE (uint32\_t id, uint8\_t \*inData)

"Generic" function to handle CAN message type PINCH\_TWIST\_SP

# 4.3.1 Detailed Description

This file contains all the function prototypes and struct definitions for the can\_driver.c file.

Attention

CAN driver for the TTK4900 Master project of Kristian Blom, spring semester of 2024. The driver specifies CAN message types relevant to the project, as well as relevant functions for the handling of transmission and reception of messages.

#### 4.3.2 Macro Definition Documentation

# 4.3.2.1 CAN\_ACC\_CMD\_OFFSET

#define CAN\_ACC\_CMD\_OFFSET 8

## 4.3.2.2 CAN\_GBL\_CMD\_OFFSET

#define CAN\_GBL\_CMD\_OFFSET 10

#### 4.3.2.3 CAN\_MOTOR\_CMD\_OFFSET

#define CAN\_MOTOR\_CMD\_OFFSET 5

# 4.3.3 Enumeration Type Documentation

## 4.3.3.1 can\_message\_type

enum can\_message\_type

CAN message types.

## Enumerator

ACC_X_TX	A message containting acc/rot X axis.
ACC_Y_TX	A message containting acc/rot Y axis.
ACC_Z_TX	A message containting acc/rot Z axis.
ACC_REG_RX	A message containting an arbitrary accelerometer register value.
ACC_REG_REQ	A message requesting an arbitrary accelerometer register value.
JOINT_POS_SP	A message containing a joint position setpoint.
MOTOR_VLT_SP	A message containting a motor voltage percent setpoint.
JOINT_POS_REQ	A message requesting the position of a joint.
JOINT_POS_TX	A message containing the position of a joint.
ACC_X_REQ	A message requesting acc/rot x axis.
ACC_Y_REQ	A message requesting acc/rot y axis.
ACC_Z_REQ	A message requesting acc/rot z axis.
GBL_ST_SET	Message contains a global state to set.
WRIST_ELBOW_SP	Message contains setpoints for the elbow and wrist joint controllers.
PINCH_TWIST_SP	Message contains setpoints for the twist and pinch joints controllers.
num_types	Dummy type for counting the number of message types, must always be last.

## 4.3.4 Function Documentation

# 4.3.4.1 can\_cmd\_handle\_axisData()

Handles incoming accelerometer axis data.

## **Parameters**

id	Incoming CAN ID
inData	Incoming CAN data

# 4.3.4.2 can\_cmd\_handle\_axisReq()

Handles an incoming request for accelerometer axis data.

#### **Parameters**

id	Incoming CAN ID
inData	Incoming CAN data

# 4.3.4.3 can\_cmd\_handle\_dualJointSp()

Handles incoming setpoints for both joints.

## **Parameters**

id	Incoming CAN ID
inData	Incoming CAN data

# 4.3.4.4 can\_cmd\_handle\_inState()

Handles incoming state information.

## **Parameters**

id	Ir	ncoming CAN ID
inDat	a Ir	ncoming CAN data

# 4.3.4.5 can\_cmd\_handle\_motorSp()

Handles an incoming motor setpoint.

#### **Parameters**

id	Incoming CAN ID
inData	Incoming CAN data

Generated by Doxygen

# 4.3.4.6 can\_cmd\_handle\_pinchTwistSp()

Handles incoming setpoints for twist and pinch joints.

#### **Parameters**

id	Incoming CAN ID
inData	Incoming CAN data

## 4.3.4.7 can\_cmd\_handle\_regReq()

Handles an incoming accelerometer read request.

### **Parameters**

id	Incoming CAN ID
inData	Incoming CAN data

## 4.3.4.8 can\_cmd\_handle\_regVal()

Handles an incoming accelerometer register message.

## **Parameters**

id	Incoming CAN ID
inData	Incoming CAN data

# 4.3.4.9 can\_cmd\_handle\_wristElbowSp()

Handles incoming setpoints for elbow and wrist joints.

## **Parameters**

id	Incoming CAN ID
inData	Incoming CAN data

## 4.3.4.10 can\_cmd\_handle\_yAcc()

# 4.3.4.11 can\_driver\_cmd\_rx0()

"Generic" function to handle CAN message type ACC\_X\_TX

#### **Parameters**

id	CAN message ID
inData	CAN message data field

## 4.3.4.12 can\_driver\_cmd\_rx1()

"Generic" function to handle CAN message type ACC\_Y\_TX

#### **Parameters**

id	CAN message ID
inData	CAN message data field

Generated by Doxygen

# 4.3.4.13 can\_driver\_cmd\_rx2()

"Generic" function to handle CAN message type ACC\_Z\_TX

## **Parameters**

id	CAN message ID
inData	CAN message data field

## 4.3.4.14 can\_driver\_cmd\_rx3()

"Generic" function to handle CAN message type ACC\_REG\_RX

### **Parameters**

id	CAN message ID
inData	CAN message data field

## 4.3.4.15 can\_driver\_cmd\_rx4()

"Generic" function to handle CAN message type ACC\_REG\_REQ

#### **Parameters**

id	CAN message ID
inData	CAN message data field

## 4.3.4.16 can\_driver\_cmd\_rx5()

"Generic" function to handle CAN message type JOINT\_POS\_SP

## **Parameters**

id	CAN message ID
inData	CAN message data field

## 4.3.4.17 can\_driver\_cmd\_rx6()

"Generic" function to handle CAN message type MOTOR\_VLT\_SP

## **Parameters**

id	CAN message ID
inData	CAN message data field

## 4.3.4.18 can\_driver\_cmd\_rx7()

"Generic" function to handle CAN message type ACC\_X\_TX

# **Parameters**

id	CAN message ID
inData	CAN message data field

## 4.3.4.19 can\_driver\_cmd\_rx8()

```
void can_driver_cmd_rx8 (
```

```
uint32_t id,
uint8_t * inData )
```

"Generic" function to handle CAN message type JOINT\_POS\_TX

#### **Parameters**

id	CAN message ID
inData	CAN message data field

## 4.3.4.20 can\_driver\_cmd\_rx9()

"Generic" function to handle CAN message type ACC\_X\_REQ

#### **Parameters**

id	CAN message ID
inData	CAN message data field

# 4.3.4.21 can\_driver\_cmd\_rxA()

"Generic" function to handle CAN message type ACC\_Y\_REQ

#### **Parameters**

id	CAN message ID
inData	CAN message data field

## 4.3.4.22 can\_driver\_cmd\_rxB()

"Generic" function to handle CAN message type ACC\_Z\_REQ

#### **Parameters**

id	CAN message ID
inData	CAN message data field

# 4.3.4.23 can\_driver\_cmd\_rxC()

"Generic" function to handle CAN message type GBL\_ST\_SET

## **Parameters**

id	CAN message ID
inData	CAN message data field

# 4.3.4.24 can\_driver\_cmd\_rxD()

"Generic" function to handle CAN message type WRIST\_ELBOW\_SP

## **Parameters**

id	CAN message ID
inData	CAN message data field

# 4.3.4.25 can\_driver\_cmd\_rxE()

"Generic" function to handle CAN message type PINCH\_TWIST\_SP

## **Parameters**

id	CAN message ID
inData	CAN message data field

Generated by Doxygen

# 4.3.4.26 can\_driver\_queue\_tx()

Queues a can message for transmit, driver internal.

#### **Parameters**

mailbox	Mailbox struct in which data will be placed
outData	Data to send (8 bytes)
id	CAN transmit ID

## 4.3.4.27 can\_driver\_send\_msg()

```
void can_driver_send_msg (
            uint8_t * data,
            uint32_t stdId,
            int dlc,
            uint8_t hwMailbox )
```

## Sends a CAN message.

#### **Parameters**

data	Data to send, max 8 bytes
stdld	Message ID required for rx handling
dlc	Number of bytes to send
hwMailbox	Hardware(!) mailbox to queue to

# 4.3.4.28 can\_interface\_queue\_tx()

Module external function for queueing a CAN message for transmit.

#### **Parameters**

mailbox	Mailbox number, must correspond to the correct message type
outData	Data to send
id	CAN transmit ID

## 4.3.4.29 can\_interface\_send\_msg()

Public function to send CAN message immediately.

#### **Parameters**

data	Data to send, max 8 byte	
id	CAN message ID	
dlc	CAN message data length	
hwMailbox	Hardware transmit mailbox to send from	

# 4.3.4.30 can\_mailbox\_clear\_flag()

Clears the newmsg flag of the given mailbox.

## **Parameters**

mailbox Mailbox to clear f	flag from
----------------------------	-----------

## 4.3.4.31 can\_mailbox\_get\_data()

Inserts the data field of the given mailbox to target. CAUTION: memcpy 8 bytes.

## **Parameters**

mailbox	Mailbox to retrieve data from
target	Pointer to data target

## 4.3.4.32 can\_mailbox\_get\_flag()

Gets the newmsg flag of the given mailbox.

# **Parameters**

mailbox	Mailbox to get
---------	----------------

#### Returns

Mailbox' newmsg flag

# 4.3.4.33 can\_mailbox\_get\_id()

Gets the CAN message ID of the given mailbox.

#### **Parameters**

mailbox	Mailbox to get ID from
---------	------------------------

#### Returns

CAN message ID

# 4.3.4.34 can\_mailbox\_set\_data()

Sets the data field of the given mailbox.

#### **Parameters**

mailbox	Mailbox to insert data into
inData	Data to insert

# 4.3.4.35 can\_mailbox\_set\_flag()

Sets the newmsg flag of the given mailbox.

#### **Parameters**

mailbox Mailbox	to set flag
-----------------	-------------

#### 4.3.4.36 can\_mailbox\_set\_id()

Sets the CAN message ID field of the given mailbox.

# Parameters

mailbox	Mailbox to insert ID
id	CAN message ID to insert

## 4.3.4.37 can\_rx\_executive()

```
void can_rx_executive ( )
```

Looks for new incoming CAN messages and handles them. MAIN LOOP ONLY.

## 4.3.4.38 can\_tx\_executive()

```
void can_tx_executive ( )
```

Looks for new CAN messages to send, sends. MAIN LOOP ONLY.

# 4.4 gpio\_driver.h File Reference

This file contains all the function prototypes for the gpio\_driver.c file.

```
#include "stdint.h"
#include "gpio.h"
#include "can_driver.h"
#include "joint_controller.h"
#include "state_machine.h"
#include "unit_config.h"
```

## **Functions**

- void gpio\_end\_switch\_handler ()
   Handler function for the rail end switch.
   void gpio\_twist\_switch\_handler ()
  - Handler function for the twist joint end switch.

## 4.4.1 Detailed Description

This file contains all the function prototypes for the gpio\_driver.c file.

Attention

GPIO driver for the TTK4900 Master project of Kristian Blom, spring semester of 2024. The driver handles GPIO interrupts from the end switch and twist joint optical sensors. The functions are called from the HAL\_GPIO\_EXTI
\_Callback function declared in stm32fxx\_hal\_gpio.h

## 4.4.2 Function Documentation

#### 4.4.2.1 gpio\_end\_switch\_handler()

```
void gpio_end_switch_handler ( )
```

Handler function for the rail end switch.

## 4.4.2.2 gpio\_twist\_switch\_handler()

```
void gpio_twist_switch_handler ( )
```

Handler function for the twist joint end switch.

# 4.5 joint controller.h File Reference

This file contains all the function prototypes and struct definitions for the joint controller.c file.

```
#include "stdint.h"
#include "math.h"
#include "tim.h"
#include "unit_config.h"
#include "uart_driver.h"
#include "motor_driver.h"
#include "can_driver.h"
#include "accelerometer_driver.h"
```

# Classes

· struct joint\_controller\_descriptor

Joint controller information database.

· struct accelerometer inData

Holds INCOMING accelerometer data, NOT part of the accelerometer driver.

#### **Functions**

• void controller\_interface\_update\_controller ()

Main function to run the controller on both joints.

float controller\_interface\_get\_setpoint (uint8\_t controllerSelect)

Public function to get the current positional setpoint of a joint.

void controller\_interface\_set\_setpoint (uint8\_t controllerSelect, float setPoint)

Public function to set the positional setpoint of a joint.

float controller\_interface\_get\_position (uint8\_t controllerSelect)

Public function to get the position of a joint.

void controller\_interface\_update\_position (uint8\_t controllerSelect)

Public function to trigger an update of the joint's position.

• void controller\_interface\_set\_position (uint8\_t controllerSelect, float position)

Public function to get the current position of a joint.

• float controller\_interface\_get\_error (uint8\_t controllerSelect)

Public function to get the current positional error of a joint.

void controller\_interface\_update\_error (uint8\_t controllerSelect)

Public function to trigger a calculation of the joint's positional error.

void controller\_interface\_set\_error (uint8\_t controllerSelect, float error)

Public function to set the positional error of a joint.

uint8\_t controller\_interface\_get\_moving (uint8\_t controllerSelect)

Public function to get the moving state value of the joint.

· void controller interface set moving (uint8 t controllerSelect)

Public function to set the moving state flag of the joint.

void controller\_interface\_clear\_moving (uint8\_t controllerSelect)

Public function to clear the moving state flag of the joint.

void controller interface set power (uint8 t controllerSelect, float power)

Public function to set the power of the joint.

void controller\_interface\_update\_power (uint8\_t controllerSelect)

Public function to trigger an update of the joint's power by PID.

float controller\_interface\_clicks\_to\_pos (uint8\_t controllerSelect)

Public function to convert the joint's associated encoder count to joint position.

• void controller\_interface\_request\_acc\_axis (uint8\_t controllerSelect, uint8\_t accSelect, char axis)

Public function to request an update from the joint's accelerometer via CAN bus; acc and rot.

int16 t controller interface acc getX (uint8 t accSelect)

Public function to get the accelerometer X axis acceleration.

• int16 t controller interface acc getY (uint8 t accSelect)

Public function to get the accelerometer Y axis acceleration.

• int16\_t controller\_interface\_acc\_getZ (uint8\_t accSelect)

Public function to get the accelerometer Z axis acceleration.

void controller\_interface\_acc\_setX (uint8\_t accSelect, int16\_t accVal)

Public function to set the accelerometer X axis acceleration.

void controller\_interface\_acc\_setY (uint8\_t accSelect, int16\_t accVal)

Public function to set the accelerometer Y axis acceleration.

void controller interface acc setZ (uint8 t accSelect, int16 t accVal)

Public function to set the accelerometer Z axis acceleration.

int16\_t controller\_interface\_rot\_getX (uint8\_t accSelect)

Public function to get the accelerometer X axis rotation rate.

int16 t controller interface rot getY (uint8 t accSelect)

Public function to get the accelerometer Y axis rotation rate.

• int16\_t controller\_interface\_rot\_getZ (uint8\_t accSelect)

Public function to get the accelerometer Z axis rotation rate.

void controller\_interface\_rot\_setX (uint8\_t accSelect, int16\_t rotVal)

Public function to set the accelerometer X axis rotation rate.

• void controller\_interface\_rot\_setY (uint8\_t accSelect, int16\_t rotVal)

Public function to set the accelerometer Y axis rotation rate.

void controller\_interface\_rot\_setZ (uint8\_t accSelect, int16\_t rotVal)

Public function to set the accelerometer Z axis rotation rate.

uint8 t controller interface acc get newX (uint8 t accSelect)

Public function to get the new X acceleration data flag.

uint8\_t controller\_interface\_acc\_get\_newY (uint8\_t accSelect)

Public function to get the new Y acceleration data flag.

uint8\_t controller\_interface\_acc\_get\_newZ (uint8\_t accSelect)

Public function to get the new Z acceleration data flag.

void controller\_interface\_acc\_set\_newX (uint8\_t accSelect)

Public function to set the new X acceleration data flag.

void controller\_interface\_acc\_set\_newY (uint8\_t accSelect)

Public function to set the new Y acceleration data flag.

void controller\_interface\_acc\_set\_newZ (uint8\_t accSelect)

Public function to set the new Z acceleration data flag.

void controller interface acc clear newX (uint8 t accSelect)

Public function to clear the new X acceleration data flag.

void controller\_interface\_acc\_clear\_newY (uint8\_t accSelect)

Public function to clear the new Y acceleration data flag.

void controller\_interface\_acc\_clear\_newZ (uint8\_t accSelect)

Public function to clear the new Z acceleration data flag.

uint8\_t controller\_interface\_rot\_get\_newX (uint8\_t accSelect)

Public function to get the new X rotation data flag.

uint8\_t controller\_interface\_rot\_get\_newY (uint8\_t accSelect)

Public function to get the new Y rotation data flag.

uint8\_t controller\_interface\_rot\_get\_newZ (uint8\_t accSelect)

Public function to get the new Z rotation data flag.

void controller interface rot set newX (uint8 t accSelect)

Public function to set the new X rotation data flag.

void controller\_interface\_rot\_set\_newY (uint8\_t accSelect)

Public function to set the new Y rotation data flag.

void controller\_interface\_rot\_set\_newZ (uint8\_t accSelect)

Public function to set the new Z rotation data flag.

void controller\_interface\_rot\_clear\_newX (uint8\_t accSelect)

Public function to clear the new X rotation data flag.

void controller\_interface\_rot\_clear\_newY (uint8\_t accSelect)

Public function to clear the new Y rotation data flag.

void controller\_interface\_rot\_clear\_newZ (uint8\_t accSelect)

Public function to clear the new Z rotation data flag.

uint8\_t controller\_interface\_get\_acc\_poll ()

Public function to poll the timer driven accelerometer poll flag.

• uint8\_t controller\_interface\_get\_mtr\_poll ()

Public function to read the timer driven motor poll flag.

void controller\_interface\_set\_acc\_poll ()

Puclic function to set the accelerometer poll flag.

void controller interface set mtr poll ()

Puclic function to set the motor poll flag.

void controller\_interface\_clear\_acc\_poll ()

Public function to clear the accelerometer poll flag.

void controller\_interface\_clear\_mtr\_poll ()

Public function to clear the motor poll flag.

- uint8\_t controller\_interface\_get\_upd\_ctrl ()
- void controller\_interface\_set\_upd\_ctrl ()
- · void controller\_interface\_clear\_upd\_ctrl ()
- uint8\_t controller\_interface\_get\_upd\_telemetry ()
- void controller\_interface\_set\_upd\_telemetry ()
- void controller\_interface\_clear\_upd\_telemetry ()
- float joint\_controller\_get\_setpoint (joint\_controller\_descriptor \*joint)
- void joint\_controller\_set\_setpoint (joint\_controller\_descriptor \*joint, float setpoint)
- float joint\_controller\_get\_position (joint\_controller\_descriptor \*joint)
- void joint\_controller\_update\_position (joint\_controller\_descriptor \*joint)
- void joint\_controller\_set\_position (joint\_controller\_descriptor \*joint, float position)
- float joint\_controller\_get\_error (joint\_controller\_descriptor \*joint)
- void joint\_controller\_update\_error (joint\_controller\_descriptor \*joint)
- void joint controller set error (joint controller descriptor \*joint, float error)
- uint8 t joint controller get moving (joint controller descriptor \*joint)
- void joint\_controller\_set\_moving (joint\_controller\_descriptor \*joint)
- void joint\_controller\_clear\_moving (joint\_controller\_descriptor \*joint)
- void joint\_controller\_set\_power (joint\_controller\_descriptor \*joint, float power)
- void joint\_controller\_update\_power (joint\_controller\_descriptor \*joint)
- float joint\_controller\_clicks\_to\_pos (joint\_controller\_descriptor \*joint)
- void joint\_controller\_adjust\_enc\_sp (joint\_controller\_descriptor \*joint)
- void joint\_controller\_request\_acc\_axis (joint\_controller\_descriptor \*joint, uint8\_t accSelect, char axis)
- float joint\_controller\_acceleration\_to\_angle (joint\_controller\_descriptor \*joint)
- int16\_t controller\_acc\_getX (accelerometer\_inData \*accSelect)
- int16 t controller acc getY (accelerometer inData \*accSelect)
- int16 t controller acc getZ (accelerometer inData \*accSelect)

- void controller\_acc\_setX (accelerometer\_inData \*accSelect, int16\_t accVal)
- void controller\_acc\_setY (accelerometer\_inData \*accSelect, int16\_t accVal)
- void controller acc setZ (accelerometer inData \*accSelect, int16 t accVal)
- int16 t controller rot getX (accelerometer inData \*accSelect)
- int16 t controller rot getY (accelerometer inData \*accSelect)
- int16\_t controller\_rot\_getZ (accelerometer\_inData \*accSelect)
- void controller\_rot\_setX (accelerometer\_inData \*accSelect, int16\_t rotVal)
- void controller rot setY (accelerometer inData \*accSelect, int16 t rotVal)
- void controller rot setZ (accelerometer inData \*accSelect, int16 t rotVal)
- uint8 t controller acc get newX (accelerometer inData \*accSelect)
- uint8 t controller acc get newY (accelerometer inData \*accSelect)
- uint8\_t controller\_acc\_get\_newZ (accelerometer\_inData \*accSelect)
- void controller\_acc\_set\_newX (accelerometer\_inData \*accSelect)
- void controller\_acc\_set\_newY (accelerometer\_inData \*accSelect)
- void controller acc set newZ (accelerometer inData \*accSelect)
- void controller acc clear newX (accelerometer inData \*accSelect)
- void controller\_acc\_clear\_newY (accelerometer\_inData \*accSelect)
- void controller\_acc\_clear\_newZ (accelerometer\_inData \*accSelect)
- uint8\_t controller\_rot\_get\_newX (accelerometer\_inData \*accSelect)
- uint8\_t controller\_rot\_get\_newY (accelerometer\_inData \*accSelect)
- uint8\_t controller\_rot\_get\_newZ (accelerometer inData \*accSelect)
- void controller rot set newX (accelerometer inData \*accSelect)
- void controller\_rot\_set\_newY (accelerometer\_inData \*accSelect)
- void controller\_rot\_set\_new7 (accelerometer\_inData \*accselect)
   void controller\_rot\_set\_newZ (accelerometer\_inData \*accselect)
- void controller\_rot\_clear\_newX (accelerometer\_inData \*accSelect)
- void controller rot clear newY (accelerometer inData \*accSelect)
- void controller\_rot\_clear\_newZ (accelerometer\_inData \*accSelect)

## 4.5.1 Detailed Description

This file contains all the function prototypes and struct definitions for the joint controller.c file.

Attention

Joint controller for the TTK4900 Master project of Kristian Blom, spring semester of 2024. The controller makes use of the motor driver to implement PID positional control of the two joints for which the relevant MCU is responsible. The accelerometer struct holds data from the joint's accelerometer, where applicable, and is always received via the CAN bus. This makes accelerometer data inherent to joint control, not the accelerometer driver itself.

Private functions are not described individually, but correspond to their public counterparts. They take a joint controller descriptor struct as argument, and are called by the public functions.

#### 4.5.2 Function Documentation

#### 4.5.2.1 controller\_acc\_clear\_newX()

#### 4.5.2.2 controller acc clear newY()

## 4.5.2.3 controller\_acc\_clear\_newZ()

## 4.5.2.4 controller\_acc\_get\_newX()

#### 4.5.2.5 controller\_acc\_get\_newY()

# 4.5.2.6 controller\_acc\_get\_newZ()

## 4.5.2.7 controller\_acc\_getX()

# 4.5.2.8 controller\_acc\_getY()

# 4.5.2.9 controller\_acc\_getZ()

# 4.5.2.10 controller\_acc\_set\_newX()

# 4.5.2.11 controller\_acc\_set\_newY()

## 4.5.2.12 controller\_acc\_set\_newZ()

# 4.5.2.13 controller\_acc\_setX()

# 4.5.2.14 controller\_acc\_setY()

## 4.5.2.15 controller\_acc\_setZ()

## 4.5.2.16 controller\_interface\_acc\_clear\_newX()

Public function to clear the new X acceleration data flag.

#### **Parameters**

accSelect The relevant accelerometer inData struct

#### 4.5.2.17 controller\_interface\_acc\_clear\_newY()

Public function to clear the new Y acceleration data flag.

#### **Parameters**

accSelect The relevant accelerometer inData struct

## 4.5.2.18 controller\_interface\_acc\_clear\_newZ()

Public function to clear the new Z acceleration data flag.

# **Parameters**

accSelect The relevant accelerometer inData struct

## 4.5.2.19 controller\_interface\_acc\_get\_newX()

Public function to get the new X acceleration data flag.

**Parameters** 

accSelect The relevant accelerometer inData struct

**Returns** 

X axis acceleration new data flag

# 4.5.2.20 controller\_interface\_acc\_get\_newY()

Public function to get the new Y acceleration data flag.

**Parameters** 

accSelect	The relevant accelerometer inData struct
accocaca	The relevant acceleration in Data struct

Returns

Y axis acceleration new data flag

# 4.5.2.21 controller\_interface\_acc\_get\_newZ()

Public function to get the new Z acceleration data flag.

**Parameters** 

accSelect	The relevant accelerometer inData struct

Returns

Z axis acceleration new data flag

# 4.5.2.22 controller\_interface\_acc\_getX()

Public function to get the accelerometer X axis acceleration.

#### **Parameters**

accSelect The relevant	accelerometer inData struct
------------------------	-----------------------------

#### Returns

X axis acceleration raw value

## 4.5.2.23 controller\_interface\_acc\_getY()

Public function to get the accelerometer Y axis acceleration.

## **Parameters**

0-14	The nelsonal construction in Data atmost
accSelect	The relevant accelerometer inData struct

#### Returns

Y axis acceleration raw value

## 4.5.2.24 controller\_interface\_acc\_getZ()

Public function to get the accelerometer Z axis acceleration.

# **Parameters**

accSelec	The relevant accelerometer inData struct
----------	--

#### Returns

Z axis acceleration raw value

# 4.5.2.25 controller\_interface\_acc\_set\_newX()

Public function to set the new X acceleration data flag.

#### **Parameters**

accSelect	The relevant accelerometer inData struct
-----------	--

# 4.5.2.26 controller\_interface\_acc\_set\_newY()

Public function to set the new Y acceleration data flag.

#### **Parameters**

accSelect The relevant accelerometer inData struct

## 4.5.2.27 controller\_interface\_acc\_set\_newZ()

Public function to set the new Z acceleration data flag.

#### **Parameters**

accSelect The relevant accelerometer inData struct

# 4.5.2.28 controller\_interface\_acc\_setX()

```
{\tt void controller\_interface\_acc\_setX} \ (
```

```
uint8_t accSelect,
int16_t accVal )
```

Public function to set the accelerometer X axis acceleration.

#### **Parameters**

accSelect	The relevant accelerometer inData struct
accVal	X axis acceleration raw value

## 4.5.2.29 controller\_interface\_acc\_setY()

Public function to set the accelerometer Y axis acceleration.

#### **Parameters**

accSelect	The relevant accelerometer inData struct
accVal	Y axis acceleration raw value

## 4.5.2.30 controller\_interface\_acc\_setZ()

Public function to set the accelerometer Z axis acceleration.

#### **Parameters**

accSelect	The relevant accelerometer inData struct
accVal	Z axis acceleration raw value

## 4.5.2.31 controller\_interface\_clear\_acc\_poll()

```
void controller_interface_clear_acc_poll ( )
```

Public function to clear the accelerometer poll flag.

## 4.5.2.32 controller\_interface\_clear\_moving()

Public function to clear the moving state flag of the joint.

**Parameters** 

controllerSelect	One of two joints available to the MCU
------------------	--

## 4.5.2.33 controller\_interface\_clear\_mtr\_poll()

```
void controller_interface_clear_mtr_poll ( )
```

Public function to clear the motor poll flag.

## 4.5.2.34 controller\_interface\_clear\_upd\_ctrl()

```
void controller_interface_clear_upd_ctrl ( )
```

## 4.5.2.35 controller\_interface\_clear\_upd\_telemetry()

```
void controller_interface_clear_upd_telemetry ( )
```

## 4.5.2.36 controller\_interface\_clicks\_to\_pos()

Public function to convert the joint's associated encoder count to joint position.

#### **Parameters**

## Returns

Joint position in rads

## 4.5.2.37 controller\_interface\_get\_acc\_poll()

```
uint8_t controller_interface_get_acc_poll ( )
```

Public function to poll the timer driven accelerometer poll flag.

## Returns

Status of the accelerometer poll flag

## 4.5.2.38 controller\_interface\_get\_error()

Public function to get the current positional error of a joint.

#### **Parameters**

controllerSelect	One of two joints available to the MCU
------------------	--

## Returns

Joint positional error in rads relative to its setpoint

## 4.5.2.39 controller\_interface\_get\_moving()

Public function to get the moving state value of the joint.

#### **Parameters**

controllerSelect	One of two joints available to the MCU

## Returns

isMoving flag

## 4.5.2.40 controller\_interface\_get\_mtr\_poll()

```
uint8_t controller_interface_get_mtr_poll ( )
```

Public function to read the timer driven motor poll flag.

Returns

Status of the motor poll flag

## 4.5.2.41 controller\_interface\_get\_position()

Public function to get the position of a joint.

#### **Parameters**

	controllerSelect	One of two joints available to the MCU
--	------------------	--

## Returns

Joint position in radians relative to its zero position

## 4.5.2.42 controller\_interface\_get\_setpoint()

Public function to get the current positional setpoint of a joint.

## **Parameters**

controllerSelect	One of two joints available to the MCU
------------------	--

#### Returns

Joint positional setpoints in radians relative to its zero position

## 4.5.2.43 controller\_interface\_get\_upd\_ctrl()

```
uint8_t controller_interface_get_upd_ctrl ( )
```

## 4.5.2.44 controller\_interface\_get\_upd\_telemetry()

```
uint8_t controller_interface_get_upd_telemetry ( )
```

#### 4.5.2.45 controller\_interface\_request\_acc\_axis()

Public function to request an update from the joint's accelerometer via CAN bus; acc and rot.

#### **Parameters**

controllerSelect	One of two joints available to the MCU
accSelect	(One of) the joint's accelerometer(s)
axis	The axis for which information is requested

## 4.5.2.46 controller\_interface\_rot\_clear\_newX()

Public function to clear the new X rotation data flag.

## **Parameters**

accSelect	The relevant accelerometer inData struct
-----------	--

## 4.5.2.47 controller\_interface\_rot\_clear\_newY()

Public function to clear the new Y rotation data flag.

#### **Parameters**

accSelect	The relevant accelerometer inData struct
-----------	--

#### 4.5.2.48 controller interface rot clear newZ()

Public function to clear the new Z rotation data flag.

#### **Parameters**

## 4.5.2.49 controller\_interface\_rot\_get\_newX()

Public function to get the new X rotation data flag.

## Parameters

accSelect	The relevant accelerometer inData struct

## Returns

Z axis rotation new data flag

## 4.5.2.50 controller\_interface\_rot\_get\_newY()

Public function to get the new Y rotation data flag.

## **Parameters**

accSelect	The relevant accelerometer inData struct

#### Returns

Y axis rotation new data flag

## 4.5.2.51 controller\_interface\_rot\_get\_newZ()

Public function to get the new Z rotation data flag.

#### **Parameters**

accSelect	The relevant accelerometer inData struct
-----------	--

#### Returns

Z axis rotation new data flag

## 4.5.2.52 controller\_interface\_rot\_getX()

Public function to get the accelerometer X axis rotation rate.

#### **Parameters**

accSelect The relevant accelerometer inData struct

#### Returns

X axis rotation rate raw value

## 4.5.2.53 controller\_interface\_rot\_getY()

Public function to get the accelerometer Y axis rotation rate.

## **Parameters**

accSelect	The relevant accelerometer inData struct
-----------	--

## Returns

Y axis rotation rate raw value

## 4.5.2.54 controller\_interface\_rot\_getZ()

Public function to get the accelerometer Z axis rotation rate.

#### **Parameters**

accSelect	The relevant accelerometer inData struct
40000000	The following accomplishments in Bata off acc

#### Returns

Z axis rotation rate raw value

## 4.5.2.55 controller\_interface\_rot\_set\_newX()

Public function to set the new X rotation data flag.

#### **Parameters**

## 4.5.2.56 controller\_interface\_rot\_set\_newY()

Public function to set the new Y rotation data flag.

#### **Parameters**

accSelect   The relevant accelerometer inData struct
--

## 4.5.2.57 controller\_interface\_rot\_set\_newZ()

Public function to set the new Z rotation data flag.

#### **Parameters**

relevant accelerometer inData struct	accSelect	
--------------------------------------	-----------	--

## 4.5.2.58 controller\_interface\_rot\_setX()

Public function to set the accelerometer X axis rotation rate.

#### **Parameters**

accSelect	The relevant accelerometer inData struct
rotVal	X axis rotation rate raw value

## 4.5.2.59 controller\_interface\_rot\_setY()

Public function to set the accelerometer Y axis rotation rate.

## Parameters

accSelect	The relevant accelerometer inData struct
rotVal	Y axis rotation rate raw value

## 4.5.2.60 controller\_interface\_rot\_setZ()

Public function to set the accelerometer Z axis rotation rate.

#### **Parameters**

accSelect	The relevant accelerometer inData struct
rotVal	Z axis rotation rate raw value

## 4.5.2.61 controller\_interface\_set\_acc\_poll()

```
void controller_interface_set_acc_poll ( )
```

Puclic function to set the accelerometer poll flag.

## 4.5.2.62 controller\_interface\_set\_error()

Public function to set the positional error of a joint.

## **Parameters**

controllerSelect	One of two joints available to the MCU
error	Joint positional error in rads

## 4.5.2.63 controller\_interface\_set\_moving()

Public function to set the moving state flag of the joint.

#### **Parameters**

o the MCU
-----------

## 4.5.2.64 controller\_interface\_set\_mtr\_poll()

```
void controller_interface_set_mtr_poll ( )
```

Puclic function to set the motor poll flag.

## 4.5.2.65 controller\_interface\_set\_position()

Public function to get the current position of a joint.

#### **Parameters**

controllerSelect	One of two joints available to the MCU
position	Joint position in rads relative to its zero position

## 4.5.2.66 controller\_interface\_set\_power()

Public function to set the power of the joint.

#### **Parameters**

controllerSelect	One of two joints available to the MCU
power	Percentage of maximum power

## 4.5.2.67 controller\_interface\_set\_setpoint()

Public function to set the positional setpoint of a joint.

#### **Parameters**

controllerSelect	One of two joints available to the MCU
setPoint	Joint positional setpoint in rads relative to its zero position

## 4.5.2.68 controller\_interface\_set\_upd\_ctrl()

```
void controller_interface_set_upd_ctrl ( )
```

## 4.5.2.69 controller\_interface\_set\_upd\_telemetry()

```
void controller_interface_set_upd_telemetry ( )
```

## 4.5.2.70 controller\_interface\_update\_controller()

```
void controller_interface_update_controller ( )
```

Main function to run the controller on both joints.

## 4.5.2.71 controller\_interface\_update\_error()

Public function to trigger a calculation of the joint's positional error.

#### **Parameters**

controllerSelect	One of two joints available to the MCU
------------------	--

## 4.5.2.72 controller\_interface\_update\_position()

Public function to trigger an update of the joint's position.

#### **Parameters**

controllerSelect   One of two joints available to the MCU	
---	--

## 4.5.2.73 controller\_interface\_update\_power()

Public function to trigger an update of the joint's power by PID.

#### **Parameters**

controllerSelect One of two joints available to the MCU

## 4.5.2.74 controller\_rot\_clear\_newX()

## 4.5.2.75 controller\_rot\_clear\_newY()

## 4.5.2.76 controller\_rot\_clear\_newZ()

## 4.5.2.77 controller\_rot\_get\_newX()

## 4.5.2.78 controller\_rot\_get\_newY()

#### 4.5.2.79 controller rot get newZ()

## 4.5.2.80 controller\_rot\_getX()

## 4.5.2.81 controller\_rot\_getY()

#### 4.5.2.82 controller\_rot\_getZ()

## 4.5.2.83 controller\_rot\_set\_newX()

## 4.5.2.84 controller\_rot\_set\_newY()

## 4.5.2.85 controller\_rot\_set\_newZ()

## 4.5.2.86 controller\_rot\_setX()

## 4.5.2.87 controller\_rot\_setY()

## 4.5.2.88 controller\_rot\_setZ()

## 4.5.2.89 joint\_controller\_acceleration\_to\_angle()

## 4.5.2.90 joint\_controller\_adjust\_enc\_sp()

#### 4.5.2.91 joint\_controller\_clear\_moving()

#### 4.5.2.92 joint\_controller\_clicks\_to\_pos()

#### 4.5.2.93 joint\_controller\_get\_error()

#### 4.5.2.94 joint\_controller\_get\_moving()

## 4.5.2.95 joint\_controller\_get\_position()

## 4.5.2.96 joint\_controller\_get\_setpoint()

Private functions are not described individually, but serve the same purpose as their public counterparts. The joint controller descriptors are static structs defined in the .c file and correspond to the unique joints of the robotic arm.

## 4.5.2.97 joint\_controller\_request\_acc\_axis()

#### 4.5.2.98 joint\_controller\_set\_error()

## 4.5.2.99 joint\_controller\_set\_moving()

## 4.5.2.100 joint\_controller\_set\_position()

## 4.5.2.101 joint\_controller\_set\_power()

## 4.5.2.102 joint\_controller\_set\_setpoint()

## 4.5.2.103 joint\_controller\_update\_error()

#### 4.5.2.104 joint\_controller\_update\_position()

#### 4.5.2.105 joint\_controller\_update\_power()

## 4.6 motor\_driver.h File Reference

This file contains all the function prototypes and struct definitions for the motor\_driver.c file.

```
#include "stdint.h"
#include "math.h"
#include "tim.h"
#include "unit_config.h"
#include "uart_driver.h"
#include "adc driver.h"
```

## **Classes**

· struct motor descriptor

Contains static and state information relevant to the operation of a motor driver.

## **Functions**

· void motor interface zero (uint8 t motorSelect)

Set to zero the motor encoder counters. This function is absolutely cursed, for whatever reason. Avoid, debug and/or reimplement.

void motor\_interface\_update\_power (uint8\_t motorSelect)

Update the power setting of the selected motor based on the relevant controller (P/I/D)

void motor\_interface\_update\_tot\_cnt (uint8\_t motorSelect)

Update the total number of registered encoder counts since init.

int32\_t motor\_interface\_get\_setpoint (uint8\_t motorSelect)

Returns the setpoint of the selected motors.

• int32\_t motor\_interface\_get\_total\_count (uint8\_t motorSelect)

Returns the number of total registered encoder counts since init.

• uint16 t motor interface get encoder count (uint8 t motorSelect)

Returns the current encoder hardware count.

uint8\_t motor\_interface\_get\_id (uint8\_t motorSelect)

Returns the numerical ID of the motor.

• int32 t motor interface get resolution (uint8 t motorSelect)

Returns the resolution of the motor in encoder clicks per rad or mm.

• int32\_t motor\_interface\_get\_delta (uint8\_t motorSelect)

Returns the most recently registered change in encoder increment.

uint8\_t motor\_interface\_get\_moving (uint8\_t motorSelect)

Returns the isMoving flag.

void motor\_interface\_set\_power (uint8\_t motorSelect, uint8\_t direction, double power)

Lets the user set the motor power setting directly.

void motor\_interface\_set\_setpoint (uint8\_t motorSelect, int32\_t setpoint)

Lets the user set the motor setpoint directly.

void motor\_interface\_set\_total\_count (uint8\_t motorSelect, int32\_t count)

Lets the user override the registered totalCount.

• void motor\_interface\_delta\_setpoint (uint8\_t motorSelect, int32\_t delta)

Lets the user increment or decrement the motor encoder setpoint.

float motor\_interface\_calculate\_torque (uint8\_t motorSelect)

Uses the motor's adc and torque constant.

void motor\_driver\_zero (motor\_descriptor \*motor)

Zero counters.

void motor\_driver\_update\_power (motor\_descriptor \*motor)

Sets the power of the selected motor based on a controller heuristic.

void motor\_driver\_update\_tot\_cnt (motor\_descriptor \*motor)

Updates the encoder total count based on the relevant heuristic.

int32 t motor driver get setpoint (motor descriptor \*motor)

Gets the total encoder count setpoint of the selected motor.

int32\_t motor\_driver\_get\_total\_cnt (motor\_descriptor \*motor)

Gets the total encoder count since init.

uint16 t motor driver get encoder cnt (motor descriptor \*motor)

Gets the current hardware encoder count.

- uint8\_t motor\_driver\_get\_id (motor\_descriptor \*motor)
- int32\_t motor\_driver\_get\_resolution (motor\_descriptor \*motor)
- uint8\_t motor\_driver\_get\_moving (motor\_descriptor \*motor)
- int32\_t motor\_driver\_get\_delta (motor\_descriptor \*motor)
- void motor\_driver\_set\_power (motor\_descriptor \*motor, uint8\_t direction, double power)

Set the power of a motor, limited by the motor's safety cap.

void motor\_driver\_set\_setpoint (motor\_descriptor \*motor, int32\_t setpoint)

Sets the total encoder count setpoint of the selected motor.

void motor\_driver\_set\_total\_count (motor\_descriptor \*motor, int32\_t count)

Sets the total encoder count of the selected motor.

void motor driver delta setpoint (motor descriptor \*motor, int32 t delta)

Changes the encoder setpoint of the relevant motor.

void motor\_driver\_set\_pwm\_dc (uint32\_t \*timerCounter, double pct)

Sets the duty cycle of the selected PWM timer as a percentage of max.

void motor driver calc safe vlt (motor descriptor \*motor)

Calculates the safe power percentage limit based on the descriptor struct.

float motor\_driver\_calculate\_torqe (motor\_descriptor \*motor, uint8\_t adcSelect)

Calculates torque from adc current and KT.

void motor driver go forward (double pct, TIM TypeDef \*mtr, int8 t polarity)

Forward is the direction of increasing encoder count.

• void motor driver go backward (double pct, TIM TypeDef \*mtr, int8 t polarity)

Backward is the direction of decreasing encoder count.

## 4.6.1 Detailed Description

This file contains all the function prototypes and struct definitions for the motor driver.c file.

Attention

Motor driver for the TTK4900 Master project of Kristian Blom, spring semester of 2024. The driver makes use of the STM32's timer peripheral to generate PWM signals driving the DRV8251A H-bridge motor drivers. The motor descriptor structs hold information relevant to the control of each motor, most importantly the safe voltage limit for each motor embedded in the robotic arm. Additionally, "trip" information such as the total number of encoder counts registered since startup, critical to the state estimation of the arm.

As all STM32s are responsible for the driving of two motors each, the .c file defines two instances of the descriptor struct, motor1 and motor2.

#### 4.6.2 Function Documentation

## 4.6.2.1 motor driver calc safe vlt()

Calculates the safe power percentage limit based on the descriptor struct.

#### **Parameters**

motor Pointer to the relevant motor struct, motor1 or motor2

## 4.6.2.2 motor\_driver\_calculate\_torqe()

Calculates torque from adc current and KT.

#### **Parameters**

*motor* Pointer to the relevant motor struct, motor1 or motor2

#### Returns

Nm torque

## 4.6.2.3 motor\_driver\_delta\_setpoint()

Changes the encoder setpoint of the relevant motor.

#### **Parameters**

motor	Pointer to the relevant motor struct, motor1 or motor2
delta	Change to encoder count setpoint

## 4.6.2.4 motor\_driver\_get\_delta()

#### **Parameters**

motor

Returns

## 4.6.2.5 motor\_driver\_get\_encoder\_cnt()

Gets the current hardware encoder count.

#### **Parameters**

motor Pointer to the relevant motor struct, motor1 or motor2

TIMx->CNT

## 4.6.2.6 motor\_driver\_get\_id()

#### **Parameters**

motorSelect

Returns

## 4.6.2.7 motor\_driver\_get\_moving()

#### **Parameters**

motor

Returns

## 4.6.2.8 motor\_driver\_get\_resolution()

## **Parameters**

motor

Returns

## 4.6.2.9 motor\_driver\_get\_setpoint()

Gets the total encoder count setpoint of the selected motor.

#### **Parameters**

motor Pointer to the relevant motor struct, motor1 or motor2

#### Returns

encoderTotalSetpoint

## 4.6.2.10 motor\_driver\_get\_total\_cnt()

Gets the total encoder count since init.

#### **Parameters**

motor Pointer to the relevant motor struct, motor1 or motor2

#### Returns

encoderTotalCount

#### 4.6.2.11 motor\_driver\_go\_backward()

Backward is the direction of decreasing encoder count.

#### **Parameters**

pct	Percentage of input voltage
mtr	Pointer to timer

## 4.6.2.12 motor\_driver\_go\_forward()

Forward is the direction of increasing encoder count.

## **Parameters**

pct	Percentage of input voltage
mtr	Pointer to timer

## 4.6.2.13 motor\_driver\_set\_power()

Set the power of a motor, limited by the motor's safety cap.

#### **Parameters**

motor	Pointer to the relevant motor struct, motor1 or motor2
direction	0 or 1 for forwards or backwards, respectively
power	percentage of input voltage

## 4.6.2.14 motor\_driver\_set\_pwm\_dc()

Sets the duty cycle of the selected PWM timer as a percentage of max.

#### **Parameters**

timerCounter	Pointer to the relevant TIMx->CNT register
pct	Percentage of maximum duty cycle

## 4.6.2.15 motor\_driver\_set\_setpoint()

Sets the total encoder count setpoint of the selected motor.

## **Parameters**

motor	Pointer to the relevant motor struct, motor1 or motor2
setpoint	Total encoder count

## 4.6.2.16 motor\_driver\_set\_total\_count()

Sets the total encoder count of the selected motor.

## **Parameters**

motor	Pointer to the relevant motor struct, motor1 or motor2	
count	Count to set	

## 4.6.2.17 motor\_driver\_update\_power()

Sets the power of the selected motor based on a controller heuristic.

## **Parameters**

<i>motor</i> Pointer to the relevant motor struct, motor1 or in	r motor2
---	----------

## 4.6.2.18 motor\_driver\_update\_tot\_cnt()

Updates the encoder total count based on the relevant heuristic.

**Parameters** 

*motor* Pointer to the relevant motor struct, motor1 or motor2

## 4.6.2.19 motor\_driver\_zero()

Zero counters.

**Parameters** 

motor | Pointer to the relevant motor struct, motor1 or motor2

## 4.6.2.20 motor\_interface\_calculate\_torque()

Uses the motor's adc and torque constant.

**Parameters** 

motorSelect 0 or 1 for motor1 or motor2 respectively

Returns

float, Nm torque

## 4.6.2.21 motor\_interface\_delta\_setpoint()

Lets the user increment or decrement the motor encoder setpoint.

## **Parameters**

motorSelect	0 or 1 for motor1 or motor2 respectively
delta	int32_t, number of encoder clicks by which the setpoint is changed

## 4.6.2.22 motor\_interface\_get\_delta()

Returns the most recently registered change in encoder increment.

#### **Parameters**

motorSelect	0 or 1 for motor1 or motor2 respectively
-------------	--

## Returns

mostRecentDelta

## 4.6.2.23 motor\_interface\_get\_encoder\_count()

Returns the current encoder hardware count.

#### **Parameters**

motorSelect	0 or 1 for motor1 or motor2 respectively

## Returns

TIMx->CNT

## 4.6.2.24 motor\_interface\_get\_id()

Returns the numerical ID of the motor.

**Parameters** 

motorSelect	0 or 1 for motor1 or motor2 respectively
-------------	--

Returns

motorID

## 4.6.2.25 motor\_interface\_get\_moving()

Returns the isMoving flag.

**Parameters** 

motorSelect	0 or 1 for motor1 or motor2 respectively
-------------	--

Returns

isMoving

## 4.6.2.26 motor\_interface\_get\_resolution()

Returns the resolution of the motor in encoder clicks per rad or mm.

**Parameters** 

Returns

resolution

## 4.6.2.27 motor\_interface\_get\_setpoint()

Returns the setpoint of the selected motors.

#### **Parameters**

motorSelect	0 or 1 for motor1 or motor2 respectively
-------------	--

#### Returns

encoder Total Setpoint

## 4.6.2.28 motor\_interface\_get\_total\_count()

Returns the number of total registered encoder counts since init.

#### **Parameters**

```
motorSelect 0 or 1 for motor1 or motor2 respectively
```

## Returns

encoderTotalCount

## 4.6.2.29 motor\_interface\_set\_power()

Lets the user set the motor power setting directly.

## **Parameters**

motorSelect	0 or 1 for motor1 or motor2 respectively
direction	0 or 1 for backwards or forwards, respectively
power	percentage of input voltage

## 4.6.2.30 motor\_interface\_set\_setpoint()

Lets the user set the motor setpoint directly.

## **Parameters**

motorSelect	0 or 1 for motor1 or motor2 respectively
setpoint	int32_t

## 4.6.2.31 motor\_interface\_set\_total\_count()

Lets the user override the registered totalCount.

#### **Parameters**

motorSelect	0 or 1 for motor1 or motor2 respectively
count	int32_t

## 4.6.2.32 motor\_interface\_update\_power()

Update the power setting of the selected motor based on the relevant controller (P/I/D)

#### **Parameters**

motorSelect	0 or 1 for motor1 or motor2 respectively	

#### 4.6.2.33 motor\_interface\_update\_tot\_cnt()

Update the total number of registered encoder counts since init.

#### **Parameters**

motorSelect	0 or 1 for motor1 or motor2 respectively
-------------	--

## 4.6.2.34 motor\_interface\_zero()

Set to zero the motor encoder counters. This function is absolutely cursed, for whatever reason. Avoid, debug and/or reimplement.

#### **Parameters**

```
motorSelect 0 or 1 for motor1 or motor2 respectively
```

## 4.7 ros\_uart\_parser.h File Reference

This file contains all the function prototypes for the ros\_uart\_parser.c file.

```
#include "string.h"
#include <stdio.h>
#include "stdint.h"
#include "unit_config.h"
#include "joint_controller.h"
#include "state_machine.h"
#include "can_driver.h"
#include "string_cmd_parser.h"
```

## **Functions**

- void ros\_interface\_set\_rxBuffer (uint8\_t \*input)
- void ros\_interface\_get\_rxBuffer (uint8\_t \*target)
- · void ros interface clear rxBuffer ()
- void ros\_interface\_set\_newMsgFlag ()
- uint8\_t ros\_interface\_get\_newMsgFlag ()
- void ros\_interface\_clear\_newMsgFlag ()
- void ros\_interface\_parse\_input ()
- void ros interface set pinchPos (float pos)

## 4.7.1 Detailed Description

This file contains all the function prototypes for the ros\_uart\_parser.c file.

Attention

ROS/UART serial interface driver for the TTK4900 Master project of Kristian Blom, spring semester of 2024. The driver makes use of the STM32's UART peripheral, as well as the string command parser module and C string libraries to do basic processing of incoming and outgoing UART data.

The parser/handler functions are triggered by the HAL UART RxCpltCallback

## 4.7.2 Function Documentation

## 4.7.2.1 ros\_interface\_clear\_newMsgFlag()

```
void ros_interface_clear_newMsgFlag ( )
```

#### 4.7.2.2 ros\_interface\_clear\_rxBuffer()

```
void ros_interface_clear_rxBuffer ( )
```

## 4.7.2.3 ros\_interface\_get\_newMsgFlag()

```
uint8_t ros_interface_get_newMsgFlag ( )
```

#### 4.7.2.4 ros\_interface\_get\_rxBuffer()

## 4.7.2.5 ros\_interface\_parse\_input()

```
void ros_interface_parse_input ( )
```

#### 4.7.2.6 ros\_interface\_set\_newMsgFlag()

```
void ros_interface_set_newMsgFlag ( )
```

## 4.7.2.7 ros\_interface\_set\_pinchPos()

## 4.7.2.8 ros\_interface\_set\_rxBuffer()

## 4.8 state\_machine.h File Reference

This file contains all the function prototypes and struct definitions for the state\_machine.c file.

```
#include "stdint.h"
#include "tim.h"
#include "unit_config.h"
#include "uart_driver.h"
#include "joint_controller.h"
#include "can_driver.h"
```

#### **Enumerations**

```
• enum global state {
 GS ERROR, GS IDLE, GS CALIBRATING, GS OPERATING,
 num gStates }
• enum calibration_state {
 CS_ERROR, CS_RAIL, CS_SHOULDER, CS_ELBOW,
 CS WRIST, CS TWIST, CS PINCH, num cStates }
```

```
Functions

    uint8_t state_interface_get_global_state ()

    void state interface set global state (uint8 t inState)

    • void state_interface_broadcast_global_state ()

    uint8_t state_interface_get_calibration_state ()

    • void state interface set calibration state (uint8 t inState)
    · void state interface broadcast calibration state ()
    void state_interface_set_es_flag ()
    • uint8_t state_interface_get_es_flag ()

    void state_interface_clear_es_flag ()

    void state_interface_set_tw_flag ()
    · uint8 t state interface get tw flag ()
    • void state_interface_clear_tw_flag ()
    • void state calibrate rail ()

    void state calibrate shoulder ()

    • void state calibrate elbow ()
    • void state_calibrate_wrist ()
    void state_calibrate_twist ()
    void state_calibrate_pinch ()
```

#### 4.8.1 **Detailed Description**

This file contains all the function prototypes and struct definitions for the state machine.c file.

Attention

Motor driver for the TTK4900 Master project of Kristian Blom, spring semester of 2024. The driver makes use of the STM32's timer peripheral to generate PWM signals driving the DRV8251A H-bridge motor drivers. The motor descriptor structs hold information relevant to the control of each motor, most importantly the safe voltage limit for each motor embedded in the robotic arm. Additionally, "trip" information such as the total number of encoder counts registered since startup, critical to the state estimation of the arm.

## 4.8.2 Enumeration Type Documentation

#### 4.8.2.1 calibration\_state

enum calibration\_state

## Enumerator

CS_ERROR	
CS_RAIL	
CS_SHOULDER	
CS_ELBOW	
CS_WRIST	
CS_TWIST	
CS_PINCH	
num_cStates	

## 4.8.2.2 global\_state

enum global\_state

## Enumerator

GS_ERROR	
GS_IDLE	
GS_CALIBRATING	
GS_OPERATING	
num_gStates	

## 4.8.3 Function Documentation

## 4.8.3.1 state\_calibrate\_elbow()

void state\_calibrate\_elbow ( )

## 4.8.3.2 state\_calibrate\_pinch()

void state\_calibrate\_pinch ( )

## 4.8.3.3 state\_calibrate\_rail()

void state\_calibrate\_rail ( )

# 4.8.3.4 state\_calibrate\_shoulder() void state\_calibrate\_shoulder ( ) 4.8.3.5 state\_calibrate\_twist() void state\_calibrate\_twist ( ) 4.8.3.6 state\_calibrate\_wrist() void state\_calibrate\_wrist ( ) 4.8.3.7 state\_interface\_broadcast\_calibration\_state() void state\_interface\_broadcast\_calibration\_state ( ) 4.8.3.8 state\_interface\_broadcast\_global\_state() void state\_interface\_broadcast\_global\_state ( ) 4.8.3.9 state\_interface\_clear\_es\_flag() void state\_interface\_clear\_es\_flag ( ) 4.8.3.10 state\_interface\_clear\_tw\_flag() void state\_interface\_clear\_tw\_flag ( ) 4.8.3.11 state\_interface\_get\_calibration\_state() uint8\_t state\_interface\_get\_calibration\_state ( )

# 4.8.3.12 state\_interface\_get\_es\_flag()

```
uint8_t state_interface_get_es_flag ( )
```

# 4.8.3.13 state\_interface\_get\_global\_state()

```
uint8_t state_interface_get_global_state ( )
```

#### 4.8.3.14 state\_interface\_get\_tw\_flag()

```
uint8_t state_interface_get_tw_flag ( )
```

# 4.8.3.15 state\_interface\_set\_calibration\_state()

# 4.8.3.16 state\_interface\_set\_es\_flag()

```
void state_interface_set_es_flag ( ) \,
```

# 4.8.3.17 state\_interface\_set\_global\_state()

# 4.8.3.18 state\_interface\_set\_tw\_flag()

```
void state_interface_set_tw_flag ( )
```

# 4.9 string\_cmd\_parser.h File Reference

This file contains all the function prototypes and struct definitions for the string\_cmd\_parser.c file.

```
#include "string.h"
#include <stdio.h>
#include <stdlib.h>
#include "stdint.h"
#include "unit_config.h"
#include "motor_driver.h"
#include "can_driver.h"
#include "joint_controller.h"
#include "state_machine.h"
#include "ros_uart_parser.h"
```

#### **Classes**

· struct string\_cmd\_processor\_args

Wrapper struct to enable a variable number of arguments to the string processor.

struct string\_cmd\_pair

Pairs a command string token with a function pointer.

#### **Macros**

- #define string\_cmd\_processor(...) string\_cmd\_processor\_wrp((string\_cmd\_processor\_args\*){\_\_VA\_←
   ARGS })
- #define NUM\_STRING\_COMMANDS 0xC

#### **Functions**

void string\_cmd\_processor\_wrp (string\_cmd\_processor\_args \*input)

Wrapper function to enable a variable number of arguments to the string processor.

void string\_cmd\_processor\_base (char \*inputString, uint8\_t stringLength)

Starting point for string processing, splits and incoming string into tokens delimited by " ".

void string\_cmd\_category\_local\_motor (uint8\_t motor, char(\*inputTokens)[64])

Handles commands to a motor/joint controller local to the STM32 connected to the serial interface.

void string\_cmd\_category\_remote\_motor (uint8\_t motor, char(\*inputTokens)[64])

Handles commands to a motor/joint controller accessible via CAN from the STM32 connected to the serial interface.

• void string\_cmd\_category\_adc ()

Handles commands to an ADC (NOTE: Not implemented)

void string\_cmd\_category\_accelerometer ()

Handles commands to an accelerometer (NOTE: Not implemented)

void string cmd rail (char(\*inputTokens)[64])

Called when "rail" token is registered; concerns the rail linear joint.

void string\_cmd\_shoulder (char(\*inputTokens)[64])

Called when "shoulder" token is registered; concerns the shoulder joint.

void string cmd elbow (char(\*inputTokens)[64])

Called when "elbow" token is registered; concerns the elbow joint.

void string\_cmd\_wrist (char(\*inputTokens)[64])

Called when "wrist" token is registered; concerns the wrist joint.

void string\_cmd\_twist (char(\*inputTokens)[64])

Called when "twist" token is registered; concerns the twist joint.

void string\_cmd\_pinch (char(\*inputTokens)[64])

Called when "pinch" token is registered; concerns the pinch joint.

void string\_cmd\_can (char(\*inputTokens)[64])

Called when "can" token is registered; concerns the CAN bus.

void string\_cmd\_stop (char(\*inputTokens)[64])

Called when "S" token is registered; soft emergency stop for all joints.

void string\_cmd\_acc1 (char(\*inputTokens)[64])

Called when "acc1" token is registered; concerns the shoulder accelerometer.

void string\_cmd\_rly (char(\*inputTokens)[64])

Called when "relay" token is registered; concerns the motor driver enable relays.

void string cmd home (char(\*inputTokens)[64])

Called when "home" token is registered; starts the home zero calibration.

void string\_cmd\_state (char(\*inputTokens)[64])

Called when "state" token is registered; lets the user set a global state.

#### **Variables**

• static string\_cmd\_pair stringCmdList [NUM\_STRING\_COMMANDS]

Pairing of string commands and handler functions.

# 4.9.1 Detailed Description

This file contains all the function prototypes and struct definitions for the string\_cmd\_parser.c file.

Attention

Keyboard input string parser for the TTK4900 Master project of Kristian Blom, spring semester of 2024. The parser makes use of the joint controller, motor driver, and the STM32's UART peripheral as well as C string libraries to enable debugging of the arm during development. It lets the user write specified commands to a serial interface such as PuTTy to control joints directly, as well as make sensor readouts on demand.

The string\_cmd\_pair list defines valid commands available to the user, which may be expanded at will. When using the arm with a serial interface, an input string beginning with one of the defined words will be handled by the corresponding function. In the interest of standardisation, all input strings limited to 64 characters.

#### 4.9.2 Macro Definition Documentation

# 4.9.2.1 NUM\_STRING\_COMMANDS

#define NUM\_STRING\_COMMANDS 0xC

# 4.9.2.2 string\_cmd\_processor

#### 4.9.3 Function Documentation

#### 4.9.3.1 string cmd acc1()

Called when "acc1" token is registered; concerns the shoulder accelerometer.

# **Parameters**

inputTokens	Arguments to parse
-------------	--------------------

# 4.9.3.2 string\_cmd\_can()

Called when "can" token is registered; concerns the CAN bus.

# **Parameters**

inputTokens
-------------

# 4.9.3.3 string\_cmd\_category\_accelerometer()

```
void string_cmd_category_accelerometer ( )
```

Handles commands to an accelerometer (NOTE: Not implemented)

#### 4.9.3.4 string\_cmd\_category\_adc()

```
void string_cmd_category_adc ( )
```

Handles commands to an ADC (NOTE: Not implemented)

# 4.9.3.5 string\_cmd\_category\_local\_motor()

Handles commands to a motor/joint controller local to the STM32 connected to the serial interface.

#### **Parameters**

motor	One of two motors, 0 or 1
inputTokens	Tokens received from the string processor

# 4.9.3.6 string\_cmd\_category\_remote\_motor()

Handles commands to a motor/joint controller accessible via CAN from the STM32 connected to the serial interface.

#### **Parameters**

motor	One of two motors, 0 or 1
inputTokens	Tokens received from the string processor

# 4.9.3.7 string\_cmd\_elbow()

Called when "elbow" token is registered; concerns the elbow joint.

# **Parameters**

inputTokens	Arguments to parse
-------------	--------------------

# 4.9.3.8 string\_cmd\_home()

Called when "home" token is registered; starts the home zero calibration.

#### **Parameters**

# 4.9.3.9 string\_cmd\_pinch()

Called when "pinch" token is registered; concerns the pinch joint.

#### **Parameters**

inputTokens	Arguments to parse
-------------	--------------------

# 4.9.3.10 string\_cmd\_processor\_base()

Starting point for string processing, splits and incoming string into tokens delimited by " ".

# **Parameters**

inputString	The string to be processed
stringLength	Length of the string to be processed

# 4.9.3.11 string\_cmd\_processor\_wrp()

Wrapper function to enable a variable number of arguments to the string processor.

# **Parameters**

input	Pointer to arguments

# 4.9.3.12 string\_cmd\_rail()

Called when "rail" token is registered; concerns the rail linear joint.

# **Parameters**

```
inputTokens Arguments to parse
```

# 4.9.3.13 string\_cmd\_rly()

Called when "relay" token is registered; concerns the motor driver enable relays.

#### **Parameters**

in	outTokens	Arguments to parse
----	-----------	--------------------

#### 4.9.3.14 string\_cmd\_shoulder()

Called when "shoulder" token is registered; concerns the shoulder joint.

# **Parameters**

```
inputTokens Arguments to parse
```

# 4.9.3.15 string\_cmd\_state()

Called when "state" token is registered; lets the user set a global state.

# **Parameters**

inputTokens

# 4.9.3.16 string\_cmd\_stop()

Called when "S" token is registered; soft emergency stop for all joints.

#### **Parameters**

inputTokens	Arguments to parse (none)	ĺ
	i i gairrettie te paire (iterre)	

# 4.9.3.17 string\_cmd\_twist()

Called when "twist" token is registered; concerns the twist joint.

# **Parameters**

inputTokens	Arguments to parse
-------------	--------------------

# 4.9.3.18 string\_cmd\_wrist()

Called when "wrist" token is registered; concerns the wrist joint.

# **Parameters**

inputTokens	Arguments to parse

#### 4.9.4 Variable Documentation

#### 4.9.4.1 stringCmdList

Pairing of string commands and handler functions.

# 4.10 uart\_driver.h File Reference

This file contains all the function prototypes for the string cmd parser.c file.

```
#include "string.h"
#include <stdio.h>
#include "usart.h"
#include "unit_config.h"
#include "string_cmd_parser.h"
#include "ros_uart_parser.h"
#include "joint_controller.h"
#include "state_machine.h"
```

#### **Functions**

```
void uart_send_string (char *str)
```

Sends a string over the UART peripheral interface.

• void uart\_parse\_hmi\_input (char \*input, uint8\_t \*buffer, uint8\_t bufferLength, uint8\_t \*bufferPos)

Reads incoming UART data and enables a keyboard based HMI to the STM32.

void uart\_parse\_ros\_input (char \*input)

DEPRECATED, replaced by ROS interface.

void uart\_hmi\_rx\_handler ()

Handles incoming UART data when the peripheral is used as HMI.

void uart\_hmi\_init ()

Initializes the UART peripheral as HMI.

void uart\_ros\_rx\_handler ()

Handles incoming UART data when the peripheral is used for ROS.

void uart\_ros\_init ()

Initializes the UART peripheral as ROS interface.

# 4.10.1 Detailed Description

This file contains all the function prototypes for the string cmd parser.c file.

Attention

UART serial interface driver for the TTK4900 Master project of Kristian Blom, spring semester of 2024. The driver makes use of the STM32's UART peripheral, as well as the string command parser module and C string libraries to do basic processing of incoming and outgoing UART data.

The parser/handler functions are triggered by the HAL\_UART\_RxCpltCallback

# 4.10.2 Function Documentation

# 4.10.2.1 uart\_hmi\_init()

```
void uart_hmi_init ( )
```

Initializes the UART peripheral as HMI.

# 4.10.2.2 uart\_hmi\_rx\_handler()

```
void uart_hmi_rx_handler ( )
```

Handles incoming UART data when the peripheral is used as HMI.

# 4.10.2.3 uart\_parse\_hmi\_input()

Reads incoming UART data and enables a keyboard based HMI to the STM32.

#### **Parameters**

input	Last incoming byte
buffer	String buffer holding the currently relevant strings
bufferLength	Length of buffer
bufferPos	Keyboard cursor position in buffer

# 4.10.2.4 uart\_parse\_ros\_input()

DEPRECATED, replaced by ROS interface.

#### **Parameters**

input

# 4.10.2.5 uart\_ros\_init()

```
void uart_ros_init ( )
```

Initializes the UART peripheral as ROS interface.

# 4.10.2.6 uart\_ros\_rx\_handler()

```
void uart_ros_rx_handler ( )
```

Handles incoming UART data when the peripheral is used for ROS.

# 4.10.2.7 uart\_send\_string()

```
void uart_send_string ( {\tt char} \ * \ str \ )
```

Sends a string over the UART peripheral interface.

# **Parameters**

str string to send

# 4.11 unit\_config.h File Reference

This file contains global information relevant to building the project for a specific STM32 in the robotic arm.

# **Macros**

- #define MTR1 TIM15
- #define MTR2 TIM1
- #define ENC1 TIM3
- #define ENC2 TIM8
- #define PWM CTR PRD 2880
- #define GLOBAL DEBUG 1
- #define VOLTAGE IN 20
- #define TORSO 0
- #define SHOULDER 1
- #define HAND 2
- #define ACTIVE\_UNIT SHOULDER
- #define UART INTERFACE 0
- #define USB\_INTERFACE 1
- #define HW INTERFACE UART INTERFACE
- #define CMD MODE TERMINAL 0
- #define CMD\_MODE\_ROS 1
- #define SW INTERFACE CMD MODE ROS
- #define CAN\_FILTER\_M 0x040
- #define CAN\_FILTERMASK\_M 0x3C0
- #define CAN FILTER A 0x000
- #define CAN FILTERMASK A 0x2E0
- #define CAN FILTER G 0x400
- #define CAN FILTERMASK G 0x7E0
- #define UART INPUT 1

# **Functions**

• void activate\_peripherals ()

# 4.11.1 Detailed Description

This file contains global information relevant to building the project for a specific STM32 in the robotic arm.

Attention

STM32 project configuration for the TTK4900 Master project of Kristian Blom, spring semester of 2024. This file specifies information unique to each STM32, i.e. the torso, shoulder and hand unit, respectively, as well as some convenience definitions common to all three.

The most important parameter is ACTIVE\_UNIT, as this flag specifies which modules will be compiled, CAN message ID filters, and safe power levels for each motor. CAUTION: Flashing an STM32 unit with the wrong ACTIVE ← UNIT flag may cause harm to the motors, as an inappropriate safe power level may be calculated for that motor.

### 4.11.2 Macro Definition Documentation

# 4.11.2.1 ACTIVE\_UNIT

#define ACTIVE\_UNIT SHOULDER

# 4.11.2.2 CAN\_FILTER\_A

#define CAN\_FILTER\_A 0x000

# 4.11.2.3 CAN\_FILTER\_G

#define CAN\_FILTER\_G 0x400

# 4.11.2.4 CAN\_FILTER\_M

#define CAN\_FILTER\_M 0x040

# 4.11.2.5 CAN\_FILTERMASK\_A

#define CAN\_FILTERMASK\_A 0x2E0

# 4.11.2.6 CAN\_FILTERMASK\_G

#define CAN\_FILTERMASK\_G 0x7E0

# 4.11.2.7 CAN\_FILTERMASK\_M

#define CAN\_FILTERMASK\_M 0x3C0

# 4.11.2.8 CMD\_MODE\_ROS

 $\#define CMD\_MODE\_ROS 1$ 

# 4.11.2.9 CMD\_MODE\_TERMINAL

#define CMD\_MODE\_TERMINAL 0

# 4.11.2.10 ENC1

#define ENC1 TIM3

# 4.11.2.11 ENC2

#define ENC2 TIM8

# 4.11.2.12 GLOBAL\_DEBUG

#define GLOBAL\_DEBUG 1

# 4.11.2.13 HAND

#define HAND 2

# 4.11.2.14 HW\_INTERFACE

#define HW\_INTERFACE UART\_INTERFACE

# 4.11.2.15 MTR1

#define MTR1 TIM15

# 4.11.2.16 MTR2

#define MTR2 TIM1

# 4.11.2.17 PWM\_CTR\_PRD

#define PWM\_CTR\_PRD 2880

# 4.11.2.18 SHOULDER

#define SHOULDER 1

# 4.11.2.19 **SW\_INTERFACE**

#define SW\_INTERFACE CMD\_MODE\_ROS

# 4.11.2.20 TORSO

#define TORSO 0

# 4.11.2.21 **UART\_INPUT**

#define UART\_INPUT 1

# 4.11.2.22 UART\_INTERFACE

#define UART\_INTERFACE 0

# 4.11.2.23 USB\_INTERFACE

#define USB\_INTERFACE 1

# 4.11.2.24 VOLTAGE\_IN

#define VOLTAGE\_IN 20

# 4.11.3 Function Documentation

# 4.11.3.1 activate\_peripherals()

void activate\_peripherals ( )

# Index

ACC_REG_REQ	accelerometer_driver.h, 24
can driver.h, 36	accl_driver_get_x_rot
ACC REG RX	accelerometer driver.h, 25
can_driver.h, 36	accl_driver_get_y_acc
ACC_X_REQ	accelerometer_driver.h, 25
can_driver.h, 36	accl driver get y rot
ACC_X_TX	accelerometer_driver.h, 25
can_driver.h, 36	accl_driver_get_z_acc
ACC_Y_REQ	accelerometer_driver.h, 26
can driver.h, 36	accl driver get z rot
ACC Y TX	accelerometer_driver.h, 26
can_driver.h, 36	accl_driver_read_byte
ACC_Z_REQ	accelerometer_driver.h, 26
can_driver.h, 36	accl_driver_read_register
ACC_Z_TX	accelerometer_driver.h, 27
can_driver.h, 36	accl_driver_set_byte
accelerometer_driver.h, 23	accelerometer_driver.h, 27
accl_driver_get_x_acc, 24	accl_interface_get_x_acc
accl_driver_get_x_rot, 25	accelerometer_driver.h, 27
accl_driver_get_y_acc, 25	accl_interface_get_x_rot
accl_driver_get_y_rot, 25	accelerometer_driver.h, 28
accl_driver_get_z_acc, 26	accl_interface_get_y_acc
accl_driver_get_z_rot, 26	accelerometer_driver.h, 28
accl_driver_read_byte, 26	accl_interface_get_y_rot
accl_driver_read_register, 27	accelerometer_driver.h, 28
accl_driver_set_byte, 27	accl_interface_get_z_acc
accl_interface_get_x_acc, 27	accelerometer_driver.h, 28
accl_interface_get_x_rot, 28	accl_interface_get_z_rot
accl_interface_get_y_acc, 28	accelerometer_driver.h, 29
accl_interface_get_y_rot, 28	accl_interface_read_byte
accl_interface_get_z_acc, 28	accelerometer_driver.h, 29
accl_interface_get_z_rot, 29	accl_interface_read_register
accl_interface_read_byte, 29	accelerometer_driver.h, 29
accl_interface_read_register, 29	accl_interface_set_byte
accl_interface_set_byte, 30	accelerometer_driver.h, 30
accelerometer_inData, 5	activate_peripherals
newXAcc, 6	unit_config.h, 109
newXRot, 6	ACTIVE_UNIT
newYAcc, 6	unit_config.h, 106
newYRot, 6	adc
newZAcc, 6	current_measurement_descriptor, 9
newZRot, 6	adc_driver.h, 30
xAcc, 7	adc_driver_calculate_current, 31
xRot, 7	adc_driver_update_measurement, 3
yAcc, 7	adc_driver_update_reading, 31
yRot, 7	adc_interface_get_current, 32
zAcc, 7	adc_interface_update_current, 32
zRot, 7	adc_driver_calculate_current
accl driver get x acc	adc_driver.h. 31

adc_driver_update_measurement	can_driver_cmd_rx4, 40
adc_driver.h, 31	can_driver_cmd_rx5, 40
adc_driver_update_reading	can_driver_cmd_rx6, 41
adc_driver.h, 31	can_driver_cmd_rx7, 41
adc_interface_get_current	can_driver_cmd_rx8, 41
adc_driver.h, 32	can_driver_cmd_rx9, 42
adc_interface_update_current	can_driver_cmd_rxA, 42
adc_driver.h, 32	can_driver_cmd_rxB, 42
Aipropi	can_driver_cmd_rxC, 43
current_measurement_descriptor, 10	can driver cmd rxD, 43
canoni_moasarement_accompton, re	can driver cmd rxE, 43
calibration_state	can driver queue tx, 44
state_machine.h, 92	can_driver_send_msg, 44
CAN ACC CMD OFFSET	CAN_GBL_CMD_OFFSET, 35
can driver.h, 35	can_interface_queue_tx, 44
can_cmd_handle_axisData	·
can_driver.h, 36	can_interface_send_msg, 45
can_cmd_handle_axisReq	can_mailbox_clear_flag, 45
can_driver.h, 36	can_mailbox_get_data, 45
can_cmd_handle_dualJointSp	can_mailbox_get_flag, 46
can driver.h, 37	can_mailbox_get_id, 46
— · · · · · · · · · · · · · · · · · · ·	can_mailbox_set_data, 46
can_cmd_handle_inState	can_mailbox_set_flag, 47
can_driver.h, 37	can_mailbox_set_id, 47
can_cmd_handle_motorSp	can_message_type, 35
can_driver.h, 37	CAN_MOTOR_CMD_OFFSET, 35
can_cmd_handle_pinchTwistSp	can_rx_executive, 47
can_driver.h, 38	can_tx_executive, 47
can_cmd_handle_regReq	GBL_ST_SET, 36
can_driver.h, 38	JOINT_POS_REQ, 36
can_cmd_handle_regVal	JOINT POS SP, 36
can_driver.h, 38	JOINT_POS_TX, 36
can_cmd_handle_wristElbowSp	MOTOR_VLT_SP, 36
can_driver.h, 38	num_types, 36
can_cmd_handle_yAcc	PINCH_TWIST_SP, 36
can_driver.h, 39	WRIST_ELBOW_SP, 36
can_driver.h, 32	can_driver_cmd_rx0
ACC_REG_REQ, 36	can driver.h, 39
ACC_REG_RX, 36	can_driver_cmd_rx1
ACC_X_REQ, 36	can driver.h, 39
ACC X TX, 36	can driver cmd rx2
ACC_Y_REQ, 36	can_driver.h, 40
ACC Y TX, 36	
ACC_Z_REQ, 36	can_driver_cmd_rx3
ACC_Z_TX, 36	can_driver.h, 40
CAN_ACC_CMD_OFFSET, 35	can_driver_cmd_rx4
can_cmd_handle_axisData, 36	can_driver.h, 40
can_cmd_handle_axisReq, 36	can_driver_cmd_rx5
can_cmd_handle_dualJointSp, 37	can_driver.h, 40
can_cmd_handle_inState, 37	can_driver_cmd_rx6
	can_driver.h, 41
can_cmd_handle_motorSp, 37	can_driver_cmd_rx7
can_cmd_handle_pinchTwistSp, 38	can_driver.h, 41
can_cmd_handle_regReq, 38	can_driver_cmd_rx8
can_cmd_handle_regVal, 38	can_driver.h, 41
can_cmd_handle_wristElbowSp, 38	can_driver_cmd_rx9
can_cmd_handle_yAcc, 39	can_driver.h, 42
can_driver_cmd_rx0, 39	can_driver_cmd_rxA
can_driver_cmd_rx1, 39	can_driver.h, 42
can_driver_cmd_rx2, 40	can_driver_cmd_rxB
can_driver_cmd_rx3, 40	

can_driver.h, 42	unit_config.h, 107
can_driver_cmd_rxC	cmdFuncPointer
can_driver.h, 43	string_cmd_pair, 21
can_driver_cmd_rxD	cmdString
can_driver.h, 43	string_cmd_pair, 21
can_driver_cmd_rxE	controller_acc_clear_newX
can_driver.h, 43	joint_controller.h, 52
can_driver_queue_tx	controller_acc_clear_newY
can_driver.h, 44	joint_controller.h, 53
can_driver_send_msg	controller_acc_clear_newZ
can_driver.h, 44	joint_controller.h, 53
CAN_FILTER_A unit_config.h, 107	controller_acc_get_newX joint_controller.h, 53
CAN FILTER G	controller_acc_get_newY
unit_config.h, 107	joint_controller.h, 53
CAN FILTER M	controller_acc_get_newZ
unit_config.h, 107	joint_controller.h, 53
CAN FILTERMASK A	controller_acc_getX
unit_config.h, 107	joint controller.h, 53
CAN FILTERMASK G	controller_acc_getY
unit_config.h, 107	joint_controller.h, 53
CAN_FILTERMASK_M	controller_acc_getZ
unit config.h, 107	joint_controller.h, 54
CAN_GBL_CMD_OFFSET	controller_acc_set_newX
can_driver.h, 35	joint_controller.h, 54
can_interface_queue_tx	controller_acc_set_newY
can_driver.h, 44	joint_controller.h, 54
can_interface_send_msg	controller_acc_set_newZ
can_driver.h, 45	joint_controller.h, 54
can_mailbox, 8	controller_acc_setX
data, 8	joint_controller.h, 54
msgld, 8	controller_acc_setY
newMsg, 8	joint_controller.h, 54
can_mailbox_clear_flag	controller acc setZ
can_driver.h, 45	joint_controller.h, 54
can_mailbox_get_data	controller_interface_acc_clear_newX
can driver.h, 45	joint controller.h, 55
can_mailbox_get_flag	controller_interface_acc_clear_newY
can_driver.h, 46	joint_controller.h, 55
can_mailbox_get_id	controller_interface_acc_clear_newZ
can_driver.h, 46	joint_controller.h, 55
can_mailbox_set_data	controller_interface_acc_get_newX
can_driver.h, 46	joint_controller.h, 55
can_mailbox_set_flag	controller_interface_acc_get_newY
can_driver.h, 47	joint_controller.h, 56
can_mailbox_set_id	controller_interface_acc_get_newZ
can_driver.h, 47	joint_controller.h, 56
can_message_type	controller_interface_acc_getX
can_driver.h, 35	joint_controller.h, 57
CAN_MOTOR_CMD_OFFSET	controller_interface_acc_getY
can_driver.h, 35	joint_controller.h, 57
can_rx_executive	controller_interface_acc_getZ
can_driver.h, 47	joint_controller.h, 57
can_tx_executive	controller_interface_acc_set_newX
can_driver.h, 47	joint_controller.h, 58
CMD_MODE_ROS	controller_interface_acc_set_newY
unit_config.h, 107	joint_controller.h, 58
CMD_MODE_TERMINAL	controller_interface_acc_set_newZ

joint_controller.h, 58	joint_controller.h, 66
controller_interface_acc_setX	controller_interface_rot_set_newZ
joint_controller.h, 58	joint_controller.h, 67
controller_interface_acc_setY	controller_interface_rot_setX
joint_controller.h, 59	joint_controller.h, 67
controller_interface_acc_setZ	controller_interface_rot_setY
joint_controller.h, 59	joint_controller.h, 67
controller_interface_clear_acc_poll	controller_interface_rot_setZ
joint_controller.h, 59	joint controller.h, 67
controller_interface_clear_moving	controller_interface_set_acc_poll
joint_controller.h, 59	joint_controller.h, 68
controller interface clear mtr poll	controller_interface_set_error
joint_controller.h, 60	joint_controller.h, 68
controller_interface_clear_upd_ctrl	controller_interface_set_moving
joint_controller.h, 60	joint_controller.h, 68
controller_interface_clear_upd_telemetry	controller_interface_set_mtr_poll
joint_controller.h, 60	joint_controller.h, 69
controller interface clicks to pos	controller interface set position
joint_controller.h, 60	joint_controller.h, 69
controller_interface_get_acc_poll	controller_interface_set_power
joint controller.h, 61	joint_controller.h, 69
controller_interface_get_error	controller_interface_set_setpoint
joint_controller.h, 61	joint_controller.h, 69
controller_interface_get_moving	controller interface set upd ctrl
joint_controller.h, 61	joint_controller.h, 70
controller_interface_get_mtr_poll	controller_interface_set_upd_telemetry
joint_controller.h, 61	joint_controller.h, 70
controller_interface_get_position	controller_interface_update_controller
joint_controller.h, 62	joint_controller.h, 70
controller_interface_get_setpoint	controller_interface_update_error
joint_controller.h, 62	joint_controller.h, 70
controller_interface_get_upd_ctrl	controller_interface_update_position
joint_controller.h, 62	joint_controller.h, 70
controller_interface_get_upd_telemetry	controller interface update power
joint controller.h, 63	joint_controller.h, 71
controller interface request acc axis	controller rot clear newX
joint_controller.h, 63	joint controller.h, 71
controller_interface_rot_clear_newX	controller_rot_clear_newY
joint_controller.h, 63	joint_controller.h, 71
controller_interface_rot_clear_newY	controller_rot_clear_newZ
joint_controller.h, 63	joint_controller.h, 71
controller interface rot clear newZ	controller_rot_get_newX
joint_controller.h, 64	joint_controller.h, 71
controller interface rot get newX	controller rot get newY
joint_controller.h, 64	joint controller.h, 71
controller interface rot get newY	controller_rot_get_newZ
joint_controller.h, 64	joint_controller.h, 72
controller_interface_rot_get_newZ	controller_rot_getX
joint_controller.h, 65	joint_controller.h, 72
controller_interface_rot_getX	controller_rot_getY
joint_controller.h, 65	joint_controller.h, 72
•	
controller_interface_rot_getY	controller_rot_getZ
joint_controller.h, 65	joint_controller.h, 72
controller_interface_rot_getZ	controller_rot_set_newX
joint_controller.h, 66	joint_controller.h, 72
controller_interface_rot_set_newX	controller_rot_set_newY
joint_controller.h, 66	joint_controller.h, 72
controller_interface_rot_set_newY	controller_rot_set_newZ

joint controller.h, 72	gpio driver.h, 48
controller_rot_setX	gpio end switch handler, 48
joint_controller.h, 73	gpio_twist_switch_handler, 48
controller_rot_setY	gpio_end_switch_handler
joint_controller.h, 73	gpio_driver.h, 48
controller_rot_setZ	gpio_twist_switch_handler
joint_controller.h, 73	gpio_driver.h, 48
conversionConst	GS CALIBRATING
current_measurement_descriptor, 10	state_machine.h, 93
CS ELBOW	GS ERROR
state_machine.h, 93	state machine.h, 93
CS ERROR	GS_IDLE
state_machine.h, 93	state_machine.h, 93
CS PINCH	
<del>-</del>	GS_OPERATING
state_machine.h, 93	state_machine.h, 93
CS_RAIL	HAND
state_machine.h, 93	unit_config.h, 108
CS_SHOULDER	hasAccelerometer
state_machine.h, 93	
CS_TWIST	joint_controller_descriptor, 14
state_machine.h, 93	HW_INTERFACE
CS_WRIST	unit_config.h, 108
state_machine.h, 93	:Oal landla
current_measurement_descriptor, 9	i2cHandle
adc, 9	imu_descriptor, 12
Aipropi, 10	imu_descriptor, 11
conversionConst, 10	i2cHandle, 12
lastMeasurement, 10	readAddr, 12
lastReading, 10	writeAddr, 12
Nadc, 10	xAccAddr, 12
Ripropi, 10	xRotAddr, 12
VrefA, 11	yAccAddr, 12
V10174, 11	yRotAddr, 13
data	zAccAddr, 13
can_mailbox, 8	zRotAddr, 13
odii_indibox, o	inputString
ENC1	string_cmd_processor_args, 22
unit_config.h, 108	intError
ENC2	joint_controller_descriptor, 14
unit_config.h, 108	isMoving
encoderInitCount	joint_controller_descriptor, 15
motor_descriptor, 18	motor descriptor, 19
encoderPreviousCount	motor_descriptor, 19
motor descriptor, 18	joint_controller.h, 49
_ · · ·	controller_acc_clear_newX, 52
encoderTimer	controller_acc_clear_newY, 53
motor_descriptor, 18	
encoderTotalCount	controller_acc_clear_newZ, 53
motor_descriptor, 18	controller_acc_get_newX, 53
encoderTotalInit	controller_acc_get_newY, 53
motor_descriptor, 19	controller_acc_get_newZ, 53
encoderTotalSetpoint	controller_acc_getX, 53
motor_descriptor, 19	controller_acc_getY, 53
	controller_acc_getZ, 54
GBL_ST_SET	controller_acc_set_newX, 54
can_driver.h, 36	controller_acc_set_newY, 54
GLOBAL_DEBUG	controller_acc_set_newZ, 54
unit_config.h, 108	controller_acc_setX, 54
global_state	controller_acc_setY, 54
state_machine.h, 93	controller_acc_setZ, 54
<del>_</del>	— ····

controller_interface_acc_clear_newX, 55	controller_rot_clear_newX, 71
controller_interface_acc_clear_newY, 55	controller_rot_clear_newY, 71
controller_interface_acc_clear_newZ, 55	controller_rot_clear_newZ, 71
controller_interface_acc_get_newX, 55	controller_rot_get_newX, 71
controller_interface_acc_get_newY, 56	controller_rot_get_newY, 71
controller_interface_acc_get_newZ, 56	controller_rot_get_newZ, 72
controller_interface_acc_getX, 57	controller_rot_getX, 72
controller_interface_acc_getY, 57	controller_rot_getY, 72
controller_interface_acc_getZ, 57	controller_rot_getZ, 72
controller_interface_acc_set_newX, 58	controller_rot_set_newX, 72
controller_interface_acc_set_newY, 58	controller_rot_set_newY, 72
controller_interface_acc_set_newZ, 58	controller_rot_set_newZ, 72
controller_interface_acc_setX, 58	controller_rot_setX, 73
controller_interface_acc_setY, 59	controller_rot_setY, 73
controller_interface_acc_setZ, 59	controller_rot_setZ, 73
controller_interface_clear_acc_poll, 59 controller interface clear moving, 59	joint_controller_acceleration_to_angle, 73 joint_controller_adjust_enc_sp, 73
<del>-</del>	
controller_interface_clear_mtr_poll, 60	joint_controller_clear_moving, 73
controller_interface_clear_upd_ctrl, 60 controller_interface_clear_upd_telemetry, 60	joint_controller_clicks_to_pos, 74 joint_controller_get_error, 74
controller_interface_clicks_to_pos, 60	joint_controller_get_enor, 74 joint_controller_get_moving, 74
controller_interface_get_acc_poll, 61	joint_controller_get_moving, 74 joint_controller_get_position, 74
controller_interface_get_error, 61	joint_controller_get_position, 74 joint_controller_get_setpoint, 74
controller_interface_get_enor, 61	joint_controller_request_acc_axis, 74
controller_interface_get_moving, 61	joint_controller_set_error, 74
controller_interface_get_position, 62	joint_controller_set_enor, 74 joint_controller_set_moving, 75
controller_interface_get_position, 62	joint_controller_set_position, 75
controller_interface_get_upd_ctrl, 62	joint_controller_set_power, 75
controller_interface_get_upd_telemetry, 63	joint_controller_set_setpoint, 75
controller_interface_request_acc_axis, 63	joint_controller_update_error, 75
controller_interface_rot_clear_newX, 63	joint_controller_update_position, 75
controller_interface_rot_clear_newY, 63	joint_controller_update_power, 76
controller_interface_rot_clear_newZ, 64	joint_controller_acceleration_to_angle
controller_interface_rot_get_newX, 64	joint controller.h, 73
controller interface rot get newY, 64	joint_controller_adjust_enc_sp
controller_interface_rot_get_newZ, 65	joint_controller.h, 73
controller_interface_rot_getX, 65	joint_controller_clear_moving
controller_interface_rot_getY, 65	joint_controller.h, 73
controller_interface_rot_getZ, 66	joint controller clicks to pos
controller_interface_rot_set_newX, 66	joint_controller.h, 74
controller_interface_rot_set_newY, 66	joint_controller_descriptor, 13
controller interface rot set newZ, 67	hasAccelerometer, 14
controller interface rot setX, 67	intError, 14
controller_interface_rot_setY, 67	isMoving, 15
controller_interface_rot_setZ, 67	jointName, 15
controller_interface_set_acc_poll, 68	Kd, 15
controller_interface_set_error, 68	Kp, 15
controller_interface_set_moving, 68	KpTi, 15
controller_interface_set_mtr_poll, 69	motorNum, 15
controller_interface_set_position, 69	posCurrent, 16
controller_interface_set_power, 69	posError, 16
controller_interface_set_setpoint, 69	posSetpoint, 16
controller_interface_set_upd_ctrl, 70	power, 16
controller_interface_set_upd_telemetry, 70	prevError, 16
controller_interface_update_controller, 70	prevPos, 16
controller_interface_update_error, 70	prevPower, 17
controller_interface_update_position, 70	sigmoidIntGain, 17
controller_interface_update_power, 71	joint_controller_get_error

joint controller.h, 74	motorPolarity, 20
joint_controller_get_moving	motorTimer, 20
joint_controller.h, 74	resolution, 20
joint_controller_get_position	torqueConst, 20
joint_controller.h, 74	voltageLimit, 20
joint_controller_get_setpoint	voltagePctCap, 20
joint_controller.h, 74	motor_driver.h, 76
joint_controller_request_acc_axis	motor_driver_calc_safe_vlt, 78
joint_controller.h, 74	motor_driver_calculate_torge, 78
joint controller set error	motor_driver_delta_setpoint, 79
joint_controller.h, 74	motor_driver_get_delta, 79
joint_controller_set_moving	motor_driver_get_encoder_cnt, 79
joint_controller.h, 75	motor_driver_get_id, 80
• —	
joint_controller_set_position	motor_driver_get_moving, 80
joint_controller.h, 75	motor_driver_get_resolution, 80
joint_controller_set_power	motor_driver_get_setpoint, 81
joint_controller.h, 75	motor_driver_get_total_cnt, 81
joint_controller_set_setpoint	motor_driver_go_backward, 81
joint_controller.h, 75	motor_driver_go_forward, 82
joint_controller_update_error	motor_driver_set_power, 82
joint_controller.h, 75	motor_driver_set_pwm_dc, 82
joint_controller_update_position	motor_driver_set_setpoint, 83
joint_controller.h, 75	motor_driver_set_total_count, 83
joint_controller_update_power	motor_driver_update_power, 83
joint_controller.h, 76	motor_driver_update_tot_cnt, 84
JOINT_POS_REQ	motor_driver_zero, 84
can_driver.h, 36	motor_interface_calculate_torque, 84
JOINT_POS_SP	motor_interface_delta_setpoint, 84
can_driver.h, 36	motor_interface_get_delta, 85
JOINT_POS_TX	motor_interface_get_encoder_count, 85
can_driver.h, 36	motor_interface_get_id, 85
jointName	motor_interface_get_moving, 86
joint_controller_descriptor, 15	motor_interface_get_resolution, 86
	motor_interface_get_setpoint, 87
Kd	motor_interface_get_total_count, 87
joint_controller_descriptor, 15	motor_interface_set_power, 87
Kp	motor_interface_set_setpoint, 88
joint_controller_descriptor, 15	motor_interface_set_total_count, 88
КрТі	motor_interface_update_power, 88
joint_controller_descriptor, 15	motor_interface_update_tot_cnt, 89
	motor_interface_zero, 89
lastMeasurement	motor_driver_calc_safe_vlt
current_measurement_descriptor, 10	motor_driver.h, 78
lastReading	motor_driver_calculate_torqe
current_measurement_descriptor, 10	motor_driver.h, 78
was at Danasat Dalta	motor_driver_delta_setpoint
mostRecentDelta	motor driver.h, 79
motor_descriptor, 19	motor driver get delta
motor_descriptor, 17	motor driver.h, 79
encoderInitCount, 18	motor_driver_get_encoder_cnt
encoderPreviousCount, 18	motor_driver.h, 79
encoderTimer, 18	motor_driver_get_id
encoderTotalCount, 18	motor_driver.h, 80
encoderTotalInit, 19	motor_driver_get_moving
encoderTotalSetpoint, 19	motor_driver.h, 80
isMoving, 19	motor_driver_get_resolution
mostRecentDelta, 19	motor_driver.h, 80
motorld, 19	motor_driver_get_setpoint
motorName, 19	motor_unver_get_setpoint

motor_driver.h, 81	joint_controller_descriptor, 15
motor_driver_get_total_cnt	motorPolarity
motor_driver.h, 81	motor_descriptor, 20
motor_driver_go_backward	motorTimer
motor_driver.h, 81	motor_descriptor, 20
motor driver go forward	msgld
motor_driver.h, 82	can_mailbox, 8
motor_driver_set_power	MTR1
motor_driver.h, 82	unit config.h, 108
motor_driver_set_pwm_dc	MTR2
motor_driver.h, 82	unit_config.h, 108
motor_driver_set_setpoint	a001g, 100
motor_driver.h, 83	Nadc
motor_driver_set_total_count	current measurement descriptor, 10
motor_driver.h, 83	newMsg
motor_driver_update_power	can_mailbox, 8
motor_driver.h, 83	newXAcc
motor_driver_update_tot_cnt	accelerometer_inData, 6
motor driver.h, 84	newXRot
motor_driver_zero	accelerometer_inData, 6
motor_driver.h, 84	newYAcc
motor_interface_calculate_torque	accelerometer_inData, 6
motor driver.h, 84	newYRot
motor_interface_delta_setpoint	accelerometer_inData, 6
motor_driver.h, 84	newZAcc
motor_interface_get_delta	accelerometer_inData, 6
motor_driver.h, 85	newZRot
motor_interface_get_encoder_count	accelerometer_inData, 6
motor_driver.h, 85	num_cStates
motor_interface_get_id	state_machine.h, 93
motor_driver.h, 85	num_gStates
motor_interface_get_moving	state_machine.h, 93
motor_driver.h, 86	NUM_STRING_COMMANDS
motor_interface_get_resolution	string_cmd_parser.h, 97
motor_driver.h, 86	num_types
motor_interface_get_setpoint	can driver.h, 36
motor_driver.h, 87	
motor_interface_get_total_count	PINCH_TWIST_SP
motor driver.h, 87	can_driver.h, 36
motor_interface_set_power	posCurrent
motor driver.h, 87	joint_controller_descriptor, 16
motor_interface_set_setpoint	posError
motor_driver.h, 88	joint_controller_descriptor, 16
motor_interface_set_total_count	posSetpoint
motor_driver.h, 88	joint_controller_descriptor, 16
motor_interface_update_power	power
motor_driver.h, 88	joint_controller_descriptor, 16
motor_interface_update_tot_cnt	prevError
motor_driver.h, 89	joint_controller_descriptor, 16
motor_interface_zero	prevPos
motor_driver.h, 89	joint_controller_descriptor, 16
MOTOR_VLT_SP	prevPower
can_driver.h, 36	joint_controller_descriptor, 17
motorld	PWM_CTR_PRD
motor_descriptor, 19	unit_config.h, 108
motorName	
motor_descriptor, 19	readAddr
motorNum	imu_descriptor, 12
	resolution

motor_descriptor, 20	state interface get tw flag
Ripropi	state machine.h, 95
current_measurement_descriptor, 10	state interface set calibration state
ros_interface_clear_newMsgFlag	state_machine.h, 95
ros_uart_parser.h, 90	state_interface_set_es_flag
ros_interface_clear_rxBuffer	state_machine.h, 95
ros_uart_parser.h, 90	state_interface_set_global_state
ros_interface_get_newMsgFlag	state_machine.h, 95
ros_uart_parser.h, 90	state_interface_set_tw_flag
ros_interface_get_rxBuffer	state_machine.h, 95
ros_uart_parser.h, 90	state_machine.h, 91
ros_interface_parse_input	calibration_state, 92
ros_uart_parser.h, 91	CS_ELBOW, 93
ros_interface_set_newMsgFlag	CS_ERROR, 93
ros_uart_parser.h, 91	CS_PINCH, 93
ros_interface_set_pinchPos	CS_RAIL, 93
ros uart parser.h, 91	CS SHOULDER, 93
ros_interface_set_rxBuffer	CS_TWIST, 93
ros_uart_parser.h, 91	CS_WRIST, 93
ros_uart_parser.h, 89	global_state, 93
ros interface clear newMsgFlag, 90	GS CALIBRATING, 93
ros_interface_clear_rxBuffer, 90	GS_ERROR, 93
ros_interface_get_newMsgFlag, 90	GS_IDLE, 93
ros_interface_get_rxBuffer, 90	GS_OPERATING, 93
ros_interface_parse_input, 91	num_cStates, 93
ros_interface_set_newMsgFlag, 91	num_gStates, 93
ros_interface_set_pinchPos, 91	state_calibrate_elbow, 93
ros_interface_set_rxBuffer, 91	state_calibrate_pinch, 93
	state_calibrate_rail, 93
SHOULDER	state_calibrate_shoulder, 93
unit_config.h, 109	state_calibrate_twist, 94
sigmoidIntGain	state_calibrate_wrist, 94
joint_controller_descriptor, 17	state_interface_broadcast_calibration_state, 94
state_calibrate_elbow	state_interface_broadcast_global_state, 94
state_machine.h, 93	state_interface_clear_es_flag, 94
state_calibrate_pinch	state_interface_clear_tw_flag, 94
state_machine.h, 93	state_interface_get_calibration_state, 94
state_calibrate_rail	state_interface_get_es_flag, 94
state_machine.h, 93	state_interface_get_global_state, 95
state_calibrate_shoulder	state_interface_get_tw_flag, 95
state_machine.h, 93	state_interface_set_calibration_state, 95
state_calibrate_twist	state_interface_set_es_flag, 95
state_machine.h, 94	state_interface_set_global_state, 95
state_calibrate_wrist	state_interface_set_tw_flag, 95
state_machine.h, 94	string_cmd_acc1
state_interface_broadcast_calibration_state	string_cmd_parser.h, 98
state_machine.h, 94	string_cmd_can
state_interface_broadcast_global_state	string_cmd_parser.h, 98
state_machine.h, 94	string_cmd_category_accelerometer
state_interface_clear_es_flag	string_cmd_parser.h, 98
state_machine.h, 94	string_cmd_category_adc
state_interface_clear_tw_flag	string_cmd_parser.h, 98
state_machine.h, 94	string_cmd_category_local_motor
state_interface_get_calibration_state	string_cmd_parser.h, 98
state_machine.h, 94	string_cmd_category_remote_motor
state_interface_get_es_flag	string_cmd_parser.h, 99
state_machine.h, 94	string_cmd_elbow
state_interface_get_global_state	string_cmd_parser.h, 99
state_machine.h, 95	<del>-</del> - ,

string_cmd_home	torqueConst
string_cmd_parser.h, 99	motor_descriptor, 20
string_cmd_pair, 21	TORSO
cmdFuncPointer, 21	unit_config.h, 109
cmdString, 21	
string_cmd_parser.h, 96	uart_driver.h, 103
NUM_STRING_COMMANDS, 97	uart_hmi_init, 104
string_cmd_acc1, 98	uart_hmi_rx_handler, 104
string_cmd_can, 98	uart_parse_hmi_input, 104
string_cmd_category_accelerometer, 98	uart_parse_ros_input, 105
string_cmd_category_adc, 98	uart_ros_init, 105
string_cmd_category_local_motor, 98	uart_ros_rx_handler, 105
string_cmd_category_remote_motor, 99	uart_send_string, 105
string_cmd_elbow, 99	uart_hmi_init
string_cmd_home, 99	uart_driver.h, 104
string_cmd_pinch, 100	uart_hmi_rx_handler
string_cmd_processor, 97	uart_driver.h, 104
string_cmd_processor_base, 100	UART_INPUT
string_cmd_processor_wrp, 100	unit_config.h, 109
string cmd rail, 100	UART_INTERFACE
string_cmd_rly, 101	unit_config.h, 109
string cmd shoulder, 101	uart_parse_hmi_input
string_cmd_state, 101	uart_driver.h, 104
string cmd stop, 102	uart_parse_ros_input
string_cmd_twist, 102	uart_driver.h, 105
string_cmd_wrist, 102	uart_ros_init
stringCmdList, 103	uart_driver.h, 105
string_cmd_pinch	uart_ros_rx_handler
string_cmd_parser.h, 100	uart_driver.h, 105
string_cmd_processor	uart_send_string
string_cmd_parser.h, 97	uart_driver.h, 105
string_cmd_processor_args, 22	unit_config.h, 105
inputString, 22	activate_peripherals, 109
stringLength, 22	ACTIVE_UNIT, 106
string cmd processor base	CAN_FILTER_A, 107
string_cmd_parser.h, 100	CAN_FILTER_G, 107
string_cmd_processor_wrp	CAN_FILTER_M, 107
string_cmd_parser.h, 100	CAN_FILTERMASK_A, 107
string_cmd_rail	CAN_FILTERMASK_G, 107
string cmd parser.h, 100	CAN_FILTERMASK_M, 107
string cmd rly	CMD_MODE_ROS, 107
string_cmd_parser.h, 101	CMD_MODE_TERMINAL, 107
string cmd shoulder	ENC1, 108
string_cmd_parser.h, 101	ENC2, 108
string_cmd_state	GLOBAL_DEBUG, 108
string_cmd_parser.h, 101	HAND, 108
string_cmd_stop	HW_INTERFACE, 108
string_cmd_parser.h, 102	MTR1, 108
string_cmd_twist	MTR2, 108
string_cmd_parser.h, 102	PWM_CTR_PRD, 108
string_cmd_wrist	SHOULDER, 109
string_cmd_parser.h, 102	SW_INTERFACE, 109
stringCmdList	TORSO, 109
string_cmd_parser.h, 103	UART_INPUT, 109
stringLength	UART_INTERFACE, 109
string_cmd_processor_args, 22	USB_INTERFACE, 109
SW INTERFACE	VOLTAGE_IN, 109
unit_config.h, 109	USB_INTERFACE
s.iii_ooiiiigiii, ioo	unit_config.h, 109

```
VOLTAGE_IN
    unit_config.h, 109
voltageLimit
    motor_descriptor, 20
voltagePctCap
    motor_descriptor, 20
VrefA
    current_measurement_descriptor, 11
WRIST_ELBOW_SP
    can_driver.h, 36
writeAddr
    imu_descriptor, 12
xAcc
    accelerometer_inData, 7
xAccAddr
    imu_descriptor, 12
xRot
    accelerometer_inData, 7
xRotAddr
    imu_descriptor, 12
yAcc
    accelerometer_inData, 7
yAccAddr
    imu_descriptor, 12
yRot
    accelerometer_inData, 7
yRotAddr
    imu_descriptor, 13
zAcc
    accelerometer_inData, 7
zAccAddr
    imu_descriptor, 13
zRot
    accelerometer_inData, 7
zRotAddr
    imu_descriptor, 13
```